

Pan I Version 4.0

An Introduction For Users

Laura M. Downs
Michael L. Van De Vanter

Computer Science Division (EECS)
University of California, Berkeley
Berkeley, California 94720

August 1991

Report No. UCB/CSD 91/659

Research sponsored in part by the Defense Advanced Research Projects Agency (DoD), monitored by Space and Naval Warfare Systems Command under Contracts N00039-84-C-0089 and N00039-88-C-0292, by IBM under IBM Research Contract No. 564516, by a gift from Apple Computer, Inc., and by the State of California MICRO Fellowship Program. Michael L. Van De Vanter was supported in part by a MICRO fellowship.

Report Documentation Page			Form Approved OMB No. 0704-0188		
Public reporting burden for the collection of information is estimated to average 1 hour per response, including the time for reviewing instructions, searching existing data sources, gathering and maintaining the data needed, and completing and reviewing the collection of information. Send comments regarding this burden estimate or any other aspect of this collection of information, including suggestions for reducing this burden, to Washington Headquarters Services, Directorate for Information Operations and Reports, 1215 Jefferson Davis Highway, Suite 1204, Arlington VA 22202-4302. Respondents should be aware that notwithstanding any other provision of law, no person shall be subject to a penalty for failing to comply with a collection of information if it does not display a currently valid OMB control number.					
1. REPORT DATE AUG 1991		2. REPORT TYPE		3. DATES COVERED 00-00-1991 to 00-00-1991	
4. TITLE AND SUBTITLE Pan I Version 4.0: An Introduction For Users		5a. CONTRACT NUMBER			
		5b. GRANT NUMBER			
		5c. PROGRAM ELEMENT NUMBER			
6. AUTHOR(S)		5d. PROJECT NUMBER			
		5e. TASK NUMBER			
		5f. WORK UNIT NUMBER			
7. PERFORMING ORGANIZATION NAME(S) AND ADDRESS(ES) University of California at Berkeley, Department of Electrical Engineering and Computer Sciences, Berkeley, CA, 94720		8. PERFORMING ORGANIZATION REPORT NUMBER			
9. SPONSORING/MONITORING AGENCY NAME(S) AND ADDRESS(ES)		10. SPONSOR/MONITOR'S ACRONYM(S)			
		11. SPONSOR/MONITOR'S REPORT NUMBER(S)			
12. DISTRIBUTION/AVAILABILITY STATEMENT Approved for public release; distribution unlimited					
13. SUPPLEMENTARY NOTES					
14. ABSTRACT Pan is a prototype and testbed for language-based editors and views. Its design addresses the needs of experienced users who manage complex objects such as large software systems. All of Pan's components are multilingual, incremental, description-driven, customizable, and extensible. Viewing is facilitated by semantics-based browsing and an object model that integrates text and structure. Pan is intended to share information with other tools, allowing integration into a larger language program, and document development environment. This document, a users manual, describes the basic operational facilities of Pan I (version 4.0), the current implementation. It explains the concepts behind Pan's editing environment, introduces editing commands, and discusses techniques for customization. Appendices list command bindings (to both keystrokes and menus), view options, and view flags.					
15. SUBJECT TERMS					
16. SECURITY CLASSIFICATION OF:			17. LIMITATION OF ABSTRACT Same as Report (SAR)	18. NUMBER OF PAGES 112	19a. NAME OF RESPONSIBLE PERSON
a. REPORT unclassified	b. ABSTRACT unclassified	c. THIS PAGE unclassified			

Abstract

Pan is a prototype and testbed for language-based editors and views. Its design addresses the needs of experienced users who manage complex objects such as large software systems. All of *Pan*'s components are multilingual, incremental, description-driven, customizable, and extensible. Viewing is facilitated by semantics-based browsing and an object model that integrates text and structure. *Pan* is intended to share information with other tools, allowing integration into a larger language, program, and document development environment.

This document, a users manual, describes the basic operational facilities of *Pan I* (version 4.0), the current implementation. It explains the concepts behind *Pan*'s editing environment, introduces editing commands, and discusses techniques for customization. Appendices list command bindings (to both keystrokes and menus), view options, and view flags.

Contents

1	Introduction	1
2	Concepts	1
2.1	Views	1
	Special Views	2
	Views vs. Windows	2
2.2	Windows	2
	The Information Panel	4
	The Editing Area	4
2.3	View Styles	4
2.4	Textual Views	4
	The Text Cursor	5
	Regions and The Text Selection	5
	Rings	5
	The Clipboard	6
	Kill Rings	6
	Marks and the Mark Stack	6
2.5	Graphical Views	6
2.6	Configuration	7
	Scopes	7
	Key Bindings	7
	Menu Bindings	8
	Operand Level Bindings and Menus	8
	Character Sets	10
	Options, Flags, and Variables	10
	Font Maps	11
2.7	Language Description	11
3	Basic Interaction	12
3.1	Getting Started	13
3.2	Executing Commands	13
3.3	Quitting	13
3.4	Supplying Arguments to Commands	13
	Numeric Prefix Arguments	13
	Prompts and Pop-Ups	14
3.5	Cancelling Commands	14
3.6	Reviewing Message History	14
3.7	Undoing Actions	15
3.8	Getting Help	15
	Apropos	16
	Help Commands	16
	Documentation Commands	17

3.9	Views and Windows	17
	Visiting Files and Other Objects	17
	Directory Editor	18
	Saving and Writing Files	19
	Manipulating Windows	20
3.10	Scrolling	20
3.11	When Things Go Wrong	21
4	Using Textual Views	22
4.1	Text Cursor Motion	22
	Moving the Cursor With the Mouse	22
	Moving Forward and Backward	22
	Moving Around in the Text Stream	23
	Mark Commands	24
4.2	The Current Operand Level	24
4.3	Operand Level Commands	25
4.4	The Textual Selection	26
4.5	Entering Text	27
4.6	Filling Text	28
4.7	Deleting Text	28
4.8	Killing Text	29
4.9	The Clipboard	30
4.10	Copying and Moving Text	30
4.11	Changing Case	31
4.12	Transposing Text	31
4.13	Searching Text	31
	Regular Expressions	31
	Balanced Bracket Commands	33
5	Using Graphical Views	33
6	Language-Oriented Services	34
6.1	Language-Based Textual Views	35
6.2	Language-Based Analysis	36
6.3	Consistency and Inconsistency	37
6.4	Operand Levels	38
6.5	The Structure Cursor	38
6.6	Setting The Structure Cursor	40
6.7	Structural Navigation	40
6.8	Language Errors	41
6.9	Editing	42
6.10	Searching in Programs	43
6.11	Queries	43
6.12	Debugging Features	43

Graphical Views	44
Other Language-Oriented Views	44
Exploring the Tree Structure	45
7 Simple Customization	45
7.1 Start-Up Processing	45
Language-Based Configuration	46
7.2 Using Scopes	47
7.3 Packaging	47
7.4 Creating Bindings	48
Creating Key Bindings	48
Creating Menu Bindings	50
Creating Operand Level Bindings	51
7.5 Getting and Setting Options	52
Setting Font Maps	53
Setting Color Maps	53
7.6 Character Sets	54
7.7 Creating and Modifying Flags	55
7.8 Lisp-Oriented Commands	56
Defining Variables and Options	57
Hooks and Notifiers	57
8 Acknowledgments	58
References	59
9 Glossary	60
A Default Key Bindings	67
A.1 Bindings by Command Name in a Text View	67
A.2 Bindings by Key in a Text View	69
A.3 Special Key Bindings in the View List	71
A.4 Special Key Bindings in the Help View	71
A.5 Special Key Bindings in a Directory Editor	71
A.6 Special Key Bindings in a Language-Based View (SIMPLE2)	71
A.7 Special Key Bindings in a Graphical View	71
B Default Menu Bindings	72
B.1 Bindings in an Ordinary Text View by Command Name	72
B.2 Bindings in an Ordinary Text View by Menu	73
B.3 Additional Menu Bindings in the View List	74
B.4 Additional Menu Bindings in the Help View	74
B.5 Additional Menu Bindings in a Directory Editor	74
B.6 Additional Menu Bindings in a Language-Based View (SIMPLE2)	74
B.7 Additional Menu Bindings in a Graphical View	74

C Operand Level Bindings in a Language-Based View (SIMPLE2)	75
D Options Defined in <i>Pan</i>	77
E Flags Defined in <i>Pan</i>	89
F Character Sets in a Text View	90
G View-Styles	91

List of Figures

1	Screen image of <i>Pan</i> showing view list, help view, and a text (T _E X) view	3
2	<i>Pan</i> with a default menu visible	9
3	Two language-based views on a program	35
4	The operand levels for SIMPLE2	39
5	The options that control structural highlighting	42
6	Bindings and names for special keys	49

1 Introduction

Pan is an editing system for text- and language-structured documents that uses the mouse, menus, and multiple windows to provide both textual and language-based browsing and editing. *Pan* is implemented in COMMON LISP with PCL and C. It runs on Sun3 and Sparc Workstations¹ under SUNOS and X11R4.

This document is an informal introduction to *Pan I* Version 4.0. It contains essential information for editing with *Pan*. All of the commands necessary for editing files, programs, and directories are described along with the key-sequences or menu choices which make them quickly accessible. With the help of this manual and the on-line help system, a new user should be able to edit text files with *Pan*. If you have not used *Emacs* or a similar editor before this, you can get started on *Pan* by focusing on the cursor motion commands (see Section 4.1) and using *Pan*'s menus to visit files, open views, use the clipboard, and get help.

The text-oriented facilities of *Pan* are modeled partially on the *Emacs* family of text editors, so users familiar with an *Emacs*-style editor will have little trouble learning *Pan*. *Pan* is extensible and customizable in the spirit of *Emacs*[7].

Some information for extending the system is included in this document. Using the information contained in the manual, any user should be able to set up a ".panrc" file which alters key- and menu-bindings and changes the default value for any options to customize the editing environment (see Section 7). For more help, you may want to contact the *Pan* group (pan-pipes@sequoia.berkeley.edu) directly. For more general background on *Pan*, consult a recent description of the project [2].

Pan also provides for manipulating and editing programs using the syntax and semantics of the language being edited. *Pan* understands descriptions of language syntax using the language-definition language *Ladle*[3]. The semantics of the language may also be described using the semantics-description language *Colander*[1]. To effectively use the language-based facilities within *Pan*, all the user should need to know is the language in question. The most useful of *Pan*'s language facilities, operand-sensitive commands, is described in this manual and in *Pan*'s help system. For more information and background on *Pan*'s language-based features, see *Coherent User Interfaces for Language-Based Editing Systems*[8].

Adding new language definitions to *Pan* is beyond the scope of this manual.

2 Concepts

This section is a brief introduction to the terminology and notation of *Pan*.

2.1 Views

A **view** represents a format for presenting the contents of or information about a file, directory, program, or other editable object. A view may also provide services with which a user may browse, explore, and modify the object being presented. For example, a text view and a graphical view of a program would be considered different views on the same program.

¹Sun Workstation is a registered trademark of Sun Microsystems, Inc.

Each view has a configurable environment which includes specifications for many aspects of the view's behavior, such as:

- key, menu, and operand-level bindings.
- definitions of character sets.
- option values, and
- flag specifications.

All views in *Pan* are named. The name of a view is composed of the name of the object being edited in that view, the type of the view, and possibly some extra qualifying information. In the current release, the name of a text view is the name of the file being edited.

Special Views

The **view list** is your doorway to *Pan*: within its edit window are the names of the views being edited. As new views are created, their names are added to this list. The view list appears in the upper left of Figure 1 on page 3, a typical workstation screen running *Pan*; it lists two other views, the help view and a view named "**manual.tex**".

The **help view** is a special text view which is used for displaying help and other information. A window on the help view appears in the upper right of Figure 1 and, currently shows the key bindings in effect for the active view. There can be only one help view at any given time (although this view can have several windows). Most commands which output information to the help view clear its contents first. See Section 3.8 for more about help facilities.

Views vs. Windows

Most commands act on the **active window** of the **active view**. The active window is the window in which the most recent keystroke or mouse action occurred. The active view is the view which owns the active window.

Views exist independently from the windows (see below) in which they are displayed. Thus there can be views that are not visible on the workstation.

In Figure 1, the text view "**manual.tex**" (containing a file of the same name) is currently active and has two separate windows open onto it.

2.2 Windows

A **window** represents the actual X window in which the contents of the view are displayed. A view may have any number of independent windows. For example, the text view "**manual.tex**" in Figure 1 has two separate windows open onto it.

A window provides a display mechanism, scroll bars, a message line, view flags, and a text cursor as seen in Figure 1. Every window also has its own operand level (see Section 2.6). All of the windows opened onto a single view share that view's contents: its bindings, its option values, and its flag specifications. A textual view (see Section 2.4) may at times have a single text selection,




Figure 1: Screen image of *Pan* showing view list, help view, and a text (TeX) view

shared by all of the view's windows, but each text window has its own independent text cursor and any window may show a different part of the view.

The horizontal scroll bar, and horizontal scrolling commands allow you to see text to the right (or left) of the current edit window (see Section 3.10). If the Text-Fill option is on then the flag “ \curvearrowright ” appears in the information panel and newly typed lines are caused to wrap around rather than being truncated (see Section 4.6).

Pan windows can be manipulated like any X window according to the window manager you are using. Closing a window from the window manager causes that window to be iconified. Closing a window from within *Pan* will cause the window to be iconified if the option *Window-Close-With-Icon* is set to be true, otherwise no icon is created. In any case the window can be reopened from the view list or by opening a view or window on that file. Internal state of the window is retained even when the window is not visible (see Section 3.9).

A window is partitioned into two areas: the information panel and the editing area.

The Information Panel

At the top of the window appears the **information panel**, which displays information about the view. It includes the view name, a **message line**, and the values of various flags. For example, Figure 1 on page 3 shows the **Object-Modified?** and **Text-Fill** flags in the “`manual.tex`” view and the **Object-Protected?** flag in the help view.

It also may display the language being edited and the operand selection level (see Section 6). Clicking the right mouse button over the name of the current operand level will bring up a menu of all of the possible operand levels for the view.

The Editing Area

Below the information panel is the **editing area**. This area includes horizontal and vertical **scroll bars**, and the actual **edit window**. Pressing the right button of the mouse over the edit window activates the *Pan* menus for that view. Selecting an item from those menus executes the command bound to that selection (see Section 3.2).

In a text window, pressing the left button of the mouse sets the text cursor to the position of the mouse (see Section 4.1). Pressing the middle button of the mouse selects the region between the text cursor and the mouse (see Section 4.4).

Windows onto textual views display text as if it were an infinite quarter-plane of characters, with newlines separating each line. Rather than wrapping lines when they reach the right-hand edge of the viewport, the lines appear truncated.

In a graphical window, there is no text cursor but the behavior of the panel, the menu selection mechanism, and the scroll bars is the same (see Section 5).

2.3 View Styles

Within *Pan* there are many different editing contexts. These different contexts are called **view styles**. Each view must be associated with a view style. For example, the help view uses the **help-view-style**, directory editors use the **dired-view-style**, and views on ordinary text files use the **text-edit-view-style**. Every *Pan* view style is either graphical or textual. For a list of all of the available view styles, see Appendix G.

All views of a particular view style inherit its configuration information (see Section 2.6). The menus, key-bindings, flags, and fonts as well as many other less visible aspects of *Pan*'s behavior provide a look and feel for each view style which may be individually tailored to provide a comfortable environment for different editing purposes.

2.4 Textual Views

Most views in *Pan* are based on the textual display and manipulation of information. Many, but not all, of the services in textual views reflect familiar styles of text-based editing. This section presents a brief overview of those services. Section 4 contains more detail.

The Text Cursor

Each text window has a single **text cursor** independent of any other cursors in other windows on the view. A text cursor appears on the screen as an inverse-video or outlined box highlighting the character selected by that cursor.

All textual insertions and deletions occur at the position to the left of the character selected by the cursor. If a command alters text not located at the cursor (for instance, by deleting the current selection), the cursor is moved to the point of change. Operations that modify text scroll the active window so that the change (and therefore the cursor) is visible.

A view's text cursor may not be visible on the screen due to scrolling or other motion. The command **Scroll-To-Cursor-Current-Window** in the **Window** menu scrolls the window so that the cursor is visible as does any cursor movement.

Regions and The Text Selection

Many of the text-oriented commands in *Pan* operate on a contiguous sequence of characters called a **region** of text.

Every textual view can have a specially designated region of text called the **selected region** or simply the **selection**. When the selection is set, it is underlined in all of the windows in which it is visible. Figure 1 on page 3 shows a selection shared by two windows. Commands that alter the contents of the view deselect the current selection.

Pan also has an **implicit selection**, namely the region between the text cursor and the top mark of the mark stack. This selection is different for each window, since each window has a different cursor. In *Emacs*, the implicit selection is the only region available, while in *Pan*, it is secondary to the visible selection. Commands that operate on the implicit selection are provided mostly for *Emacs* compatibility. The command **Select-Region-Dot-To-Mark** which is usually bound to the key sequence "**Esc** **^W**" makes the implicit selection into the selection.

Pan's style of selection is similar to, but not the same as, X's. Clicking the middle button of the mouse selects and underlines the region between the cursor and the mouse, but placing or dragging the cursor does *not* affect the selection. The selection, the position of the mouse, and the position of the text cursor are all independent.

Rings

A **ring** is a circular bounded stack. Adding an item to a ring pushes the other items just like a bounded stack. The oldest value in the stack may be discarded to preserve the boundedness.

Rings can also be "cycled", where the top value is moved to the position of the oldest value, and all of the other values move up—the second youngest becoming the top. Cycling a ring by n values moves the n th element (modulo the size of the ring) to the top. The top value in a ring is called the "contents" of the ring.

Both the clipboard and the kill rings are implemented as rings.

The Clipboard

The **clipboard**—a holder for regions of text—is shared among all views. A selection can be copied (or cut) to the clipboard and then pasted in another view. These operations are modeled on the Macintosh² user interface. Unlike the Macintosh clipboard, *Pan*'s clipboard is a ring that contains several items. The size of the clipboard is determined by the value of the option **Clipboard-Max-Size**.

Kill Rings

The **kill ring** is a repository for deleted text. Commands that kill text place the killed text into the kill ring. This text can be retrieved at a later time by yanking it.

The size of the kill ring is determined by the value of the option **Killring-Max-Size**.

In *Pan*, the kill ring is local to a view rather than global to all views as it is in *Emacs*. The kill ring and the clipboard are independent entities; cutting text to the clipboard does not affect the contents of the kill ring and killing text does not affect the clipboard. However, if the option **Kills-To-Clipboard** is set, then the “Kill-” commands use the global clipboard instead of the kill ring and text killing and yanking is then effectively global.

Marks and the Mark Stack

A **mark** is a character position in a textual view. Marks associate with the character to the left of the position; when text is deleted, affected marks migrate to the beginning of the deletion.

Each view has a stack of marks called the **mark stack**. Marks in *Pan* are used for two purposes: to remember a cursor position, and to construct regions. The top mark on the stack is usually referred to as “the mark”.

2.5 Graphical Views

For any program or other structure-based view, a **graphical view** of the internal tree representation may be created. Graphical views may be generated on the entire internal tree or on any subtree of it. The contents of the nodes in the graph may contain the names of the nodes or other information about the node, depending on the command used to generate the view.

The contents of the text stream from which the view was generated can not be altered from within the graphical view. In the current version of *Pan*, the graph is a display only and not a graphical editor; not even the structural cursor may be set from within a graphical view.

Graphical views may be navigated by thumbing the window to a fixed position by pressing the middle mouse button over the scroll bars or by “Zoom-”ing in and out.

A graphical view also contains a **global image** in the upper-left corner of the window. Within this image a miniature of the entire graph or subgraph being viewed is displayed, and the region of the graph which is currently visible in the window is outlined. This global image may be resized or toggled on and off.

Graphical views of the tree structure of programs are the only kind of graphical view implemented at present. Because the graphical view functions only as a display of the tree representation

²Macintosh is a registered trademark of Apple Computer, Inc.

and has no interactive capability, its usefulness is limited mostly to system extenders, particularly to authors of language descriptions.

Other types of graphical views are possible, such as a program call graph, but have not yet been implemented. This sort of view would have more practical use to the programmer.

2.6 Configuration

Most of the user interface and much of the operation of *Pan* may be customized. Each view in *Pan* is a separate editing context in which many aspects of *Pan*'s behavior and user interface may be configured. The default configuration of *Pan* is defined by a collection of declarations in the same format as those a user might write to customize one or more of *Pan*'s editing contexts (Section 7). A **binding** associates a sequence of keyboard or mouse actions with a command. *Pan* provides for adding key- and menu-bindings, setting options, configuring operand-level bindings, describing character sets, creating and manipulating flags, and creating new editing environments for specific uses. The on-line help system provides documentation for any configurable *Pan* command, option, or other object. All of these are scoped to provide flexible control of the editing environment.

Scopes

There are normally three possible **scopes**³ for any binding or option:

- **:global** - global to all views,
- **:view-style** - restricted to all views of a particular view style, and
- **:view** - local to a single view.

Any configurable data can lie within any of these scopes. Therefore they are either *local* to a view, shared by all views of a particular view style, or *global* to all views. Thus, every view may have its own set of key bindings, and even its own menus and menu selections. Naturally, local bindings take precedence over global bindings.

Key Bindings

Key bindings associate keystroke sequences with commands. They provide the user with a quick way to execute commands. Most commonly used commands are bound to some key sequence. *Pan*, like *Emacs*, provides a live keyboard. Keystrokes (including mouse buttons and special keyboard keys) are read until a valid binding is detected. When a binding is detected, the associated command is executed.

A key binding associates a keystroke sequence with a command. These key sequences are generally one or two characters but there is no restriction on how long a binding can be. The keys "Escape", "~X", "~C", and "~Z" are, by convention, used as prefix keys. The "Shift" and "Control" keys are modifier keys rather than prefix keys. Any keystroke sequence may be bound to any command. In your configuration, you can set aside other keys to be prefixes as well as those

³The scope **:buffer**, which consists of all views on a single editable object, is also defined internally but is not often used for configuration.

mentioned above. However, if you bind a key sequence to a command, that binding will shadow any previously defined bindings which have that sequence as a prefix or which are a prefix of that sequence. For example, if you bind “`^A ^X`” to a command, you will no longer have the usual binding for “`^A`” or if you bind “`^X`” to a command, you will no longer have any of the key bindings for which “`^X`” is a prefix.

Any key sequence can be bound in any scope. A binding in a `:view-style` scope will shadow a binding to the same sequence in the `:global` scope; a binding in the `:view` scope will shadow a binding in its `:view-style` scope or the `:global` scope. Thus each view-style or view can have its own customized editing environment.

Mouse buttons and function keys can be bound to commands just like the standard keyboard keys. In fact, it is the standard binding of the right-most mouse button to **Execute-Menu** that implements *Pan*’s menu selection service. The function keys available vary between keyboards and key mappings. *Pan*’s default key bindings for the special keyboard keys generally reflect the standard usage for the keys. For example the “Undo”, “Cut”, and “Paste” keys on the left and the “Up-” and “Down-Arrow” keys on the right are bound to commands which reflect their purpose.

The default bindings for mouse buttons are similar to the X bindings. Appendix A lists *Pan*’s default key bindings.

Menu Bindings

Each view has a default menu, often inherited from the view’s view style, but bindable in any scope. A *Pan* menu contains a collection of **menu bindings**, each of which associate menu item selections with commands. A menu binding consists of a menu, a menu item, and a command name.

The advantages of a menu binding are that you don’t need to remember a command name or a key binding to execute the command, because you need only recognize the command in the menu and select the corresponding menu item with the mouse. Because of this, menu bindings are extremely useful for the new user. Like key bindings, menus and menu bindings may be scoped by `:view`, `:view-style`, or `:global`. The default menus associated with a view appear when the right button of the mouse is pressed while the mouse is positioned over the edit window. Figure 2 on page 9 shows a menu selection being made.


A menu binding is designated by a menu title and a selection name, denoted typographically by **MenuTitle: SelectionName**. For example, the selection **Menus** in Figure 2 is bound to the command **Display-Default-Menu**. It is not necessary for the selection name to be identical to the name of the command bound to the selection.

Default menu bindings are best discovered by mousing around. Appendices B.1–B.4 list the default menu bindings for a text view, for the view list, and for the help view.

As with key bindings, any command may be bound to a menu item. Each different menu or submenu is globally defined. The binding of a submenu or a menu selection to a menu affects the global definition of the menu. However, menus may be copied and the copy may be altered to achieve a `:view-style` or `:view` local configuration.

Operand Level Bindings and Menus

Operand level bindings associate generic operations, such as **Cursor-Forward** or **Delete** with

Figure 2: *Pan* with a default menu visible

operands designated by the current operand level (see Section 6). A keystroke sequence or menu item can be bound to a command that implements a generic operation. The generic operation, in turn, consults the operand level bindings and the current operand level of the active window to determine the actual command to execute.

Each window has a **current operand level** which can be used to control the actions of operand-generic operations. The generic operations are: **Cursor-Forward**, **Cursor-Backward**, **Cursor-To-First**, **Cursor-To-Last**, **Cursor-In**, **Cursor-Out**, **Select**, **Cursor-To-Mouse**, **Mouse-Extend**, and **Delete** as well as the search operations: **Query-Replace-All**, **Replace-All**, **Cursor-Search-Forward**, and **Cursor-Search-Backward**. The **Oplevel-Menu** command, which is normally bound to “**C Mouse-Right**” brings up a menu which contains all of the operand-level operations for the current level.

For example, the key “**Right-Arrow**” is bound to the command **Oplevel-Cursor-Forward**. If the current operand level is “**Character**”, and the binding of the generic command **Cursor-Forward** at the level “**Character**” is the command **Next-Character**, then **Oplevel-Cursor-Forward** will execute **Next-Character**.

Setting the operand level is a bit like changing modes in a moded editor, except that it *only* affects the generic bindings. The current operand level persists across operations. In pure text editing, the operand level is of limited usefulness. When editing views that have a richer operand domain, for example programs supported by one of *Pan*'s language descriptions, the ability to select and navigate using the operand level bindings is a bonus. For instance, a programming language might define operand levels such as "Expression", "Statement", and "Declaration". Figure 4 on page 39 shows the operand-level choices for a language-based view.

The current operand level affects only those commands that consult it. These commands are syntactically distinguished by containing the phrase "Oplevel-" in their name. An operand level binding is designated by a generic operation and an operand level denoted typographically by *Operation at level "OperandLevel"*.

As with key-bindings, operand level bindings may also be scoped by `:view`, `:view-style`, or `:global` to provide a specialized editing environment for different views.

Character Sets

A **character set** has a name and may contain any number of ASCII characters. For example, the set **indentation-characters** contains the characters { **Tab Space** }. The default character sets are listed in Appendix F. Any character may belong to any number of sets or to no set. Character sets are used to recognize white-space, to identify matching brackets, and to find the extent of a word among other things. Commands for finding and altering the contents of a character set are described in Section 7.6.

Character set definitions are scoped and local definitions shadow global definitions. For example, the set **word-characters** is defined differently in the help view than in text views. The command **Display-Char-Sets** will display the contents of the character sets in the active view.

Options, Flags, and Variables

An **option** is implemented as a variable which is used to control user-configurable settings. Option variables, flags, and variables are provided for controlling and extending the system.

Option variables, or simply "options" are used to control user-configurable settings. They are implemented as strongly-typed, scoped variables. Appendix D lists the basic options, their types, and their default values. The effective value of an option is obtained using the command **Announce-Option-Variable** (see section 7.5). All options along with their values for a particular view may be listed with the command **Display-Option-Variables**.

A **flag** is an option that can be made visible. Flags can be displayed on the information panel by adding the associated option to a list of flag specifications along with an "on-icon" and an "off-icon". When the flag is set, i.e. the associated option is non-nil, then the "on-icon" is displayed in the information panel. The "off-icon" is often invisible. For instance, if the **Object-Modified?** flag is set (meaning that the text of a view has been modified since last saved), a "*" appears on the information panel. Appendix E lists the default set of flags, together with their display properties.

A *Pan* **variable** is scoped, like an option, but is used for internals and not accessible to the user.

Font Maps

Every character in *Pan*'s internal text representation contains a font code. This code determines the font used when the character is displayed in a window. Each view has an associated **font map**, which associates font codes with internal font descriptors. A font map contains from 1 to 8 entries.

Internally, fonts are referred to as "font 0", "font 1", etc. The first element of the list (font 0) is the **default font**; unspecified font codes revert to the default font.

Pan maintains a default font map option which may be scoped. You can alter these defaults by setting the option **Text-Window-Fontmap** globally, in the scope of the view-style you want to affect, or in a particular view.

The standard specification for a font map is a zero-indexed list of font names containing from 1 to 8 names, for example:

```
("-adobe-times-medium-i-normal--17-120-100-100-p-84-iso8859-1"
 "-b&h-lucida-medium-r-normal-sans-12-120-75-75-p-71-iso8859-1"
 "-adobe-times-bold-i-normal--17-120-100-100-p-86-iso8859-1")
```

Standard text views use only the default font. Section 6.2 describes a more elaborate use of font maps in conjunction with language-structured documents.

2.7 Language Description

Adding new **language descriptions** is the most important of *Pan*'s extension mechanisms. A *Pan* language description is distinct from a language definition, which is written by the designer of the language, although it typically relies heavily on the definition. The language description is a configuration mechanism that enables *Pan* to deliver services to the user which are based on the underlying language structure and which can be tailored to the particular language. There may be more than one *Pan* description for a given language definition, each delivering different services (e.g. demonstration descriptions **SIMPLE** and **SIMPLE2**).

Language descriptions have many components, but they fall roughly into three categories: A syntax description (for the syntactic analyzer), a semantic description (for the semantic analyzer), and a specification of the editing interface (for the user's services).

- The syntax description consists of a *Ladle* file plus panic declarations. The *Ladle* description consists of a specification of the lexical tokens followed by a description of the grammar of the language in a format similar to YACC input format. These are accompanied by directives to *Pan* on how to construct the abstract syntax tree [3].
- The semantic description is optional and consists of one or more ".col" (*Colander*) files. A *Colander* description consists of a set of goals associated with the rules of the grammar, each of which specifies a context-sensitive constraint that should be satisfied at each instance of a grammar rule in the internal tree. These are expressed in the language *Colander* (a Logical Constraint Grammar [1]), and are accompanied by supporting declarations and function definitions.

- the editing interface is configured mostly in a COMMON LISP run-time library file for each language named “<language>-mode.cl” This file may configure nearly all of the parameters described in Section 2.6, especially language-specific operand levels, operand menus, font maps, and other special-purpose functionality.

Further information on constructing these interface description files is found in Section 7.

Errors in a program being edited (with respect to the language description) are divided into two categories in *Pan*’s underlying implementation: syntactic errors and unsatisfied constraints. **Syntactic errors** are structural inconsistencies between the program and the *Ladle* syntax description. **Unsatisfied constraints**, also referred to sometimes (somewhat inappropriately) as semantic errors, are unsatisfied contextual constraints in the program, as specified in a *Colander* semantic description. These may include, for example, type checking (based on the language’s definition) and naming conventions (based on the language’s intended use).

Default error definition and handling is automatically provided by *Pan*. However, the error handling mechanism may be configured for each specific language description. For example both syntactic errors and unsatisfied constraints may be treated as one via a single operand level definition (e.g. as in demonstration language SIMPLE). Alternately, the two basic categories may be divided further, for example unsatisfied language constraints vs. stylistic constraints.

When you are editing a file with a complete *Pan* language description, *Pan* maintains:

- an internal structural representation of the program based on the *Ladle* description of the language which is updated incrementally with each analysis
- a database of semantic information, structural annotations, and other data derived from the program and the *Colander* description, also updated with each analysis
- a configuration that controls the look and feel of user interaction with the language as well as a number of user services that exploit the derived information

3 Basic Interaction

This section is an introduction to general kinds of interaction with the *Pan* system. At the beginning of each subsection is a list of the commands discussed, together with their default bindings. Control keys are represented by prepending the character “^” in front of the key, e.g., “Control-X” is shown as “^X”, and the keystroke sequence “Control-X” “Control-F” is shown as “^X ^F”. The prefix “Escape” is denoted “Esc”.

Menu bindings are denoted by `MenuTitle: SelectionName` where `MenuTitle` is the title of the menu which appears at the top of the menu and `SelectionName` is the name of an item appearing in the menu. Operand-level bindings are denoted by `Command at level “OperandLevel”`. All of the configurable bindings are described in Section 2.6 and details of creating and altering bindings are contained in Section 7.4.

3.1 Getting Started

When *Pan* is started, the files named on the command line are read in as *Pan* text views and prepared for editing. Once initialization is complete, the view list will appear. Section 7.1 provides more specific details about *Pan*'s start-up processing.

3.2 Executing Commands

Execute-Command	Esc x
Execute-Menu	Mouse-Right

The simplest and most common way to execute a command is via a key or menu binding (see Section 2.6), but it is also possible to execute any *Pan* command by name. To execute a *Pan* command by name, type "Esc x", the keystroke sequence bound by default to **Execute-Command**. **Execute-Command** prompts for a command name. The prompt is *case-sensitive*, so you have to capitalize the command name correctly or it won't be recognized.

To select an item from a view's default menu, hold down "Mouse-Right" within the edit window of the view in which you want to execute the command. When the menu appears, continue to hold down the button and move the mouse over the menu item of your choice. When the item you want is highlighted, release the button. If you choose a sub-menu, do not release the button but move to the appropriate item in the sub-menu and repeat the process.

3.3 Quitting

Exit-Editor	^X ^C
Exit-Editor	View List: Quit
Interrupt-Editor	^X ^Z

Exit-Editor is the normal method for terminating a *Pan* session. When modified views exist you will be asked whether they should be saved.

Interrupt-Editor stops the system and control goes to a break loop in the underlying COMMON LISP. You can resume editing by typing ":cont". This is usually used for debugging.

3.4 Supplying Arguments to Commands

There are three ways to provide arguments to *Pan* commands: by a numeric prefix argument, by setting the current selection, or by responding to a prompt. The actual method used depends on the particular command. Commands that can use a numeric argument normally check for the presence of a numeric prefix, while commands that require textual arguments may use the selection or may prompt for an argument.

Numeric Prefix Arguments

Prefix	^U
--------	----

The behavior of many commands can be altered by supplying **numeric prefix** arguments. In most cases, the argument is interpreted as a repetition factor, and the effect of the command is simply repeated. **Prefix** reads the prefix arguments from the keyboard. There are two ways to type such arguments: by typing a sequence of digits, or by repeating the keystroke sequence bound to **Prefix**. In the latter case, each repetition corresponds to multiplication by the value of the option **Prefix-Arg-Multiplier** (default value 4). For example, the key sequence “**^N**” is normally bound to the command **Next-Line** which takes a prefix argument. Typing “**^U ^N**” would cause the cursor to move forward four lines; typing “**^U ^U ^N**” would cause the cursor to move forward 16 lines; typing “**^U 3 ^N**” would cause the cursor to move forward 3 lines.

Prompts and Pop-Ups

Pan prompts for input by making a small **pop-up window** appear on the screen. The pop-up remains on the screen until you complete the input. When a pop-up is visible, *Pan* is effectively stopped until the pop-up is dismissed. Pop-ups may be manipulated by the window manager, though.

Pop-ups have one or more “buttons” on their lower edge: clicking the left button of the mouse over one of those areas completes and confirms the prompt. When typing a textual argument into a pop-up, standard UNIX editing characters serve to edit the input. Pop-ups for textual arguments are confirmed by selecting a button or by hitting the “Return” key. The “Return” key has the same effect as clicking on the button with the bold outline.

3.5 Cancelling Commands

Editor-Error	^G
Editor-Error	^C ^G
Editor-Error	Esc ^G
Editor-Error	^X ^G
Editor-Error	^Z ^G
Editor-Error	“Cancel” on Pop-ups

To cancel a keystroke sequence, type “**^G**” with any prefix. To cancel a menu selection, move the mouse cursor outside (away from) the menu, and release the mouse button. When responding to a prompt, select the “**Cancel**” button.

Once a command is initiated, there is little you can do to stop it. If the command takes more than an instant to complete, the mouse cursor image, normally an arrow, may be replaced by a clock.

3.6 Reviewing Message History

Prev-Message-Current-Window	Esc p
Next-Message-Current-Window	Esc n

These commands allow you to review the messages which have been displayed in a window's message line. Each time one of these commands is invoked, a message is displayed on the message line along with an index that indicates which message is being displayed; the most recent message is indexed [0], the one previous to that is [-1], etc.. A history of the significant messages which have been printed is stored for each window. The size of this history is controlled by the option **Window-Message-History-Size** whose default value is 32 messages. Insignificant messages are not part of the history, e.g. empty announcements that clear the message line and messages announcing that the system is garbage collecting.

3.7 Undoing Actions

Undo	[^] X u
Undo	L4
Undo	Undo: Undo
Redo	[^] X r
Redo	Undo: Redo
Sub-Undo	Undo: Sub-Undo
Sub-Redo	Undo: Sub-Redo

The **undo** facilities of *Pan* allow you to undo the most recent action or series of similar actions. The effect of undoing an action is to return the text to the state it was in before that action was executed.

Invoking **Undo** will undo the most recent action. Invoking **Undo** a second time will undo the action previous to that. The command **Redo** will redo the last command undone. For instance, typing a series of characters and then invoking **Undo** will remove the entire series of characters just typed. Invoking the command **Redo** after the first **Undo** restores the text removed by the first **Undo**. A sequence of consecutive **Undo** commands are coalesced into a single action and so may be undone as one action after other commands have been executed.

Both **Undo** and **Redo** use the numeric prefix argument to determine the number of previous actions to undo or redo. The option **Undo-Size** specifies the maximum number of consecutive commands which can be undone.

Sub-Undo and **Sub-Redo** operate on commands that are subdivided into separate commands such as **Replace-All** and **Query-Replace-All**. **Sub-Undo** will undo the last portion of the previous command (i.e. the last replacement in **Replace-All**).

3.8 Getting Help

Reset-Help	Help View: Reset Help
Visit-Help-View	Help

Pan is largely self-documenting. Each view has an associated **Help** menu that provides access to the help information supplied by the system. This information will be displayed in the **help view**—a special view known to the system. Figure 1 on page 3 shows the help view in the upper right-hand

corner of the screen. The help view acts like a normal text view, except that it is altered only by the help commands.

Most help commands delete any pre-existing text in the help view before adding their contribution. Others, such as **Describe-Selection** add additional information to the view. The information in the help view can be saved to a text file at any time. The command **Reset-Help** empties the help view. If there is not already a window open onto the help view, the command **Visit-Help-View** opens one window onto the help view, otherwise it brings the already open window to the front of the screen. This command is implicitly called every time information is printed to the help view.

Apropos

Apropos-String
Display-Apropos-Index

Help: Apropos
Not bound

The “Apropos-” family of commands associate a keyword with a list of command names. For instance, invoking the command **Apropos-String** and supplying the argument “clipboard” lists, in the help view, all of the commands that use the clipboard. **Display-Apropos-Index**⁴ will list all of the possible “Apropos” arguments and their corresponding commands.

Help Commands

Document-Symbol	Help View: Describe
Visit-Symbol-Definition	Help View: Visit Definition
Visit-Symbol-Definition	Esc .
Display-Objects	^X ^B
Display-All-Key-Bindings	Help⇒This View⇒Keys: Display All
Display-Key-Binding	Help⇒This View⇒Keys: Key -> Command
Display-Key-Bindings-For-Command	Help⇒This View⇒Keys: Command -> Key
Display-Default-Menu	Help⇒This View: Default Menu
Display-Operand-Level-Bindings	Help⇒This View⇒Operand Cmds.: By Level
Display-Operand-Command-Bindings	Help⇒This View⇒Operand Cmds.: By Command
Display-Operand-Level-Menus	Help⇒This View: Operand Menus
Display-Option-Variables	Help⇒This View: Options
Display-Flags	Help⇒This View: Flags
Display-Char-Sets	Help⇒This View: Char. Sets
Display-Objects	Help⇒Pan: Objects Being Viewed
Display-Language-List	Help⇒Pan: Language Descriptions Loaded
Display-Commands	Help⇒Pan: Commands Available
Display-Auto-Load	Help⇒Pan: Filename Auto-Load Map
Display-Auto-Exec	Help⇒Pan: Filename Auto-Exec Map
Display-Version	Help⇒Pan: Version

⁴Many help commands are of limited value to new or casual users, and are therefore not bound to the default menus. Invoking the command **Debug** adds auxiliary menus in which more help commands are available.

Display-Bug-Report-Info	Help⇒Pan: How To Report Bugs
Display-View-Class-Key-Bindings	Not bound
Display-Configuration	Not bound
Display-File-Ids	Not bound
Display-Hooks	Not bound
Display-Notifiers	Not bound

Commands beginning with “Display-” simply list the names of all things of a given type for the current view. (e.g., all commands or all options). Commands in the **This View** sub-menu refer to things which are scoped and the commands give the values for those things in the current scope. Commands in the **Pan** sub-menu refer to things which are global to the editor. For more about **Auto-Load** and **Auto-Exec** see Section 7.1. For more about hooks and notifiers see section 7.8, and for setting options see Section 7.5.

Documentation Commands

Display-Command-Documentation	Not bound
Display-Operand-Level-Documentation	Not bound
Display-Operand-Command-Documentation	Not bound
Display-Option-Documentation	Not bound
Display-Char-Set-Documentation	Not bound
Display-Variable-Documentation	Not bound
Display-Constant-Documentation	Not bound
Display-Function-Documentation	Not bound
Display-Macro-Documentation	Not bound
Display-Hook-Documentation	Not bound

“-Documentation” commands display the names of all things of a given type along with a documentation string.

3.9 Views and Windows

The commands presented in this section support basic view and window management.

Visiting Files and Other Objects

Visit-Selected-View	View List: Visit View
Visit-Selected-View	f in View List
Visit-File	^X ^F
Visit-File	View List: Visit New
Visit-File	Store: Visit New...
Protected-Visit-File	^X ^R
Visit-Backup	Not bound
Visit-Checkpoint	Not bound

Visit-Directory	<code>^X ^D</code>
Visit-Directory	<code>^X d</code>
Set-Working-Directory	Not bound
Visit-View	<code>^X b</code>
Visit-View-List	<code>R7</code>
Scratch-View	View List: New Scratch
Rename-View	Not bound
Remove-Selected-View	View List: Remove
Remove-Selected-View	x in View List
Remove-View	<code>^X k</code>
Remove-View	View: Remove
Remove-Object	Not bound

To edit a file, one must first create a view onto it with the command **Visit-File** or the command **Dired-Visit** (see below). **Visit-File** prompts for a file name. If a view does not already exist for that file, a new view is created for it and the file is read and prepared for editing.

To visit an existing view, you can use the **Visit-Selected-View** command from the view list. This command normally appears as **Visit View** in the **View List** menu. It is used by first selecting a name in the view list.

To edit a directory, either use **Visit-File** with the name of the directory or use the command **Visit-Directory**. The **Visit-Directory** command allows you to specify a pattern for file names. For example, if you give it the argument `~/pan/*.tex`, it will give you the directory editor for `~/pan` listing only files whose names end in `.tex`.

Visit-View prompts for the name of a view and opens a window for that view if it is in the view list. **Scratch-View** creates a new text view named `***scratch**` that is not associated with any file.

The **Remove-Object** command removes all views which share the given editable object and offers you a chance to save any changes.

Remove-Selected-View and **Remove-View** remove one view from the view list. If that is the only active view that exists on that data then it is removed as in **Remove-Object**. Once a **Remove-** command has been executed, all of the state associated with the removed object is lost.

Directory Editor

Dired-Visit	Dired: Visit
Dired-Visit	f
Dired-Visit-Read-Only	Dired: Visit Read Only
Dired-Visit-Read-Only	<code>^R</code>
Dired-Mark-Selection	Dired: Mark
Dired-Mark-Selection	d
Dired-Unmark-Selection	Dired: Unmark
Dired-Unmark-Selection	u
Dired-Delete-Files	Dired: Delete marked files

Dired-Delete-Files	x
Dired-Mark-Editor-Files	Dired: Mark backup files
Dired-Mark-Editor-Files	#
Revert-Object	Dired: Reread directory
Revert-Object	g
Visit-Directory	^X ^D
Visit-Directory	^X D

The **directory editor** view-style is useful for editing objects which are directories. To visit any file in the directory, select that file with the mouse or by normal cursor movement and invoke the command **Dired-Visit**. The command **Dired-Visit-Read-Only** works the same except that the view is protected so that its contents cannot be altered.

The directory editor allows you to mark files to be deleted with the command **Dired-Mark-Selection** then to delete those files with the command **Dired-Delete-Files**. **Dired-Mark-Editor-Files** marks for deletion all of the files in the directory which were created by *Pan* as backups.

Saving and Writing Files

Save-Object	^X ^S
Save-Object	Store: Save
Preserve-All-Objects	^X Return
Exit-Editor	^X ^C
Save-Object-Copy-As	^X ^W
Save-Object-Copy-As	Store: Save Copy As ...
Write-Selection-To-File	Text Edit⇒File: Write Selection To ...
Append-Selection-To-File	Text Edit⇒File: Append Selection To ...
Revert-Object	^X Backspace
Revert-Object	Store: Revert
Backup-Object	Not bound
Checkpoint-Object	Not bound
Revert-Object-To-Backup	Not bound
Revert-Object-To-Checkpoint	Not bound
Toggle-Object-Protection	^X ^Q
Toggle-Object-Protection	Text Edit: Toggle Protection
Toggle-Object-Modification	Not bound

Save-Object saves the contents of the current view in its associated file; **Preserve-All-Objects** save s all of the modified views being edited. **Exit-Editor** performs the standard termination sequence of saving modified views and exiting. The commands **Preserve-All-Objects** and **Exit-Editor** prompt for whether a particular view is to be written to file.

All of the commands **Save-Object-Copy-As**, **Write-Selection-To-File**, and **Append-Selection-To-File** prompt for the name of a file to write. The command **Save-Object-Copy-As** does not rename the view.

Revert-Object replaces the contents of the object underlying the view in memory with the stored copy.

Toggle-Object-Protection toggles the **Object-Protected?** option in the view. When this option is set, the flag “@” appears on the information panel and you will be prevented from modifying or writing that file. This option is set by default when you commence editing a file for which you do not have permission to write. Toggling the **Object-Protected?** flag does not affect the permissions on the stored file itself.

If the option **Backup-Object?** is set, then the first time a file is saved, a backup of the original is created. The command **Revert-Object-To-Backup** can be used to restore the original file.

The file will be checkpointed after a number of modifications given by the option **Checkpoint-Modification-Interval**. The command **Visit-Checkpoint** allows you to edit the last checkpoint of the file and the command **Revert-Object-To-Checkpoint** allows you to revert the file to that state.

Toggle-Object-Modification allows you to toggle the **Object-Modified?** which appears as the flag “★” in the information panel.

Manipulating Windows

Open-A-Window-In-View	Not bound
Open-Another-Window-In-View	^X 2
Open-Another-Window-In-View	Window: Open Another
Close-Current-Window	^X 0
Close-Current-Window	Window: Close
Redraw-Current-Window	^L
Redraw-Current-Window	Window: Redraw

When you visit a view that has no visible windows, *Pan* will reopen the view’s most recently closed window. If the view has no windows, a new window is created. To open a second (or third, or fourth, ...) window onto a view, execute the command **Open-Another-Window-In-View**.

Closing a window causes it to disappear from the screen. If the option **Window-Close-With-Icon** is set, then the window will be iconified when it is closed from within *Pan*. Closing a window from the window manager will always cause it to be iconified. The internal state of the view is retained even when it has no windows so that windows onto that view can be reopened later. You can not remove the view list.

Windows are reopened using the same commands as are used for opening new windows. They are reopened in last-in, first-out order relative to the order in which they were closed.

Redraw-Current-Window redraws the active window.

3.10 Scrolling

Forward-Vscroll-Current-Window	^V
Backward-Vscroll-Current-Window	Esc v
Left-Hscroll-Current-Window	^X <
Right-Hscroll-Current-Window	^X >

Scroll-To-Cursor-Current-Window

Window: Scroll To Cursor

Pan's scrolling behavior is a simplified version of the X scrolling protocols. The scroll bars in a window respond to simple scroll commands. For vertical scrolling, pressing the left button in the vertical scroll bar scrolls the window toward the end of the file, the right button scrolls the window towards the beginning of the file, and the middle button thumbs the window to the point indicated by the scroll "bubble". Holding down the middle button and moving the mouse allows you to scan, or "thumb", the file.

When scrolling horizontally, pressing the left button in the horizontal scroll bar scrolls the window toward the end of the line, the right button scrolls the window towards the beginning of the line, and the middle button thumbs the window to the point indicated by the scroll bubble.

The first four of the above commands permit scrolling from the keyboard instead of from the mouse. During vertical scrolling, when the option **Text-Window-Proportional-Scroll** is set to be true (in COMMON LISP, 't), the amount that the edit window is scrolled depends upon the distance between the mouse cursor and the top of the scroll bar. For small movements, place the mouse cursor near the top of the scroll bar. For larger movements, place the mouse cursor near the bottom of the scroll bar. To scroll an entire screen, place the mouse cursor opposite to the last line of text visible in the window.

When the option **Text-Window-Proportional-Scroll** is set to be false (in COMMON LISP, 'nil), the vertical scrolling commands scroll the window by a full screen at a time.

To "thumb" the view to an absolute position, place the mouse cursor in the scroll bar and press **Mouse-Middle**. The window will be scrolled to the position corresponding to the relative distance between the top of the scroll bar and the position of the mouse cursor.

Scrolling the screen by a full screen at a time can also be achieved by using **Forward-Vscroll-Current-Window** and **Backward-Vscroll-Current-Window**. Both of those commands consult the numeric prefix argument to determine the number of screens to move.

Left-Hscroll-Current-Window and **Right-Hscroll-Current-Window** are keyboard variants of the horizontal scrolling commands.

The command **Scroll-To-Cursor-Current-Window** redraws the window and scrolls so that the cursor appears in the center of the window. The position of the cursor is *not* affected by scrolling. Therefore, scrolling may cause the cursor to be not visible in the window.

Any cursor motion or alteration of the text will scroll the window so that the cursor is visible.

3.11 When Things Go Wrong

```
:panic
:resume
```

Pan has been remarkably (well, reasonably) robust throughout its long development period. Most problems are routinely handled by printing a message on the message line of the active view. However, provisions have been made for recovering from major catastrophes.

We'd probably all agree that a catastrophe has occurred if *Pan* failed either by returning to the underlying COMMON LISP system or by dying altogether. Fortunately, the first rarely happens, and the second won't occur without returning to COMMON LISP.

If an unanticipated COMMON LISP error occurs, *Pan* enters a COMMON LISP break loop. If you do somehow end up in a COMMON LISP break loop, a prompt will appear in the tool window in which the system is running. (If *Pan* is running from a menu, the prompt will appear in the console.). The prompt will look like “{*nn*}” or “*nn* ⇒” where “*nn*” is a small integer.

In the first case (“{*nn*}”), the system is in a COMMON LISP break loop. You can recover from the error by typing the COMMON LISP expression `:resume` which returns the system to the normal command evaluation loop or `:panic` which executes the normal code for saving the modified views and then exits the system. Naturally, the circumstances of such an error should be noted and passed on to the developers of *Pan*. (Mail to pan-bug@sequoia.berkeley.edu)

The second case (“*nn* ⇒”) is more serious. In fact, the session is almost over. All that you can do is to type `:panic`.

4 Using Textual Views

This section describes the basic text-oriented services that are available in *Pan*'s textual views. These correspond in many ways to traditional text editors, and users of *Emacs* will find much that is familiar. *Pan*'s language-based services (also available in textual views) are described in Section 6.

4.1 Text Cursor Motion

Announce-Text-Cursor-Info

^X =

The command `Announce-Text-Cursor-Info` can be used to display status information in the information panel about the text cursor in the active window.

Moving the Cursor With the Mouse

Oplevel-Cursor-To-Mouse
Cursor-To-Mouse
Cursor-To-Mouse
Mouse-Select-Fullword
Mouse-Select-Line

^C Mouse-Left
Mouse-Left
Cursor-To-Mouse at level “Character”
Cursor-To-Mouse at level “Word”
Cursor-To-Mouse at level “Line”

The left button of the mouse is bound to the command `Cursor-To-Mouse` which sets the cursor to the character selected by the mouse icon. This command does not affect the current selection.

The corresponding operand level command `Oplevel-Cursor-To-Mouse` is normally bound to the key sequence “^C Mouse-Left”. When the operand level is set to “Character”, it invokes the command `Cursor-To-Mouse`. At different operand levels, `Oplevel-Cursor-To-Mouse` selects the operand under the mouse and places the text cursor at the beginning of the selection.

Moving Forward and Backward

Oplevel-Cursor-Forward

^C ^F

Oplevel-Cursor-Forward	Right-Arrow
Next-Character	[^] F
Next-Character	Cursor-Forward at level "Character"
Next-Word	Esc f
Next-Word	Cursor-Forward at level "Word"
Next-Line	[^] N
Next-Line	Cursor-Forward at level "Line"
Oplevel-Cursor-Backward	[^] C [^] B
Oplevel-Cursor-Backward	Left-Arrow
Previous-Character	[^] B
Previous-Character	Cursor-Backward at level "Character"
Previous-Word	Esc b
Previous-Word	Cursor-Backward at level "Word"
Previous-Line	[^] P
Previous-Line	Cursor-Backward at level "Line"
Oplevel-Cursor-In	[^] C [^] I
Oplevel-Cursor-In	Down-Arrow
Next-Line	Cursor-In at level "Character"
Next-Line	Cursor-In at level "Word"
Next-Line	Cursor-In at level "Line"
Oplevel-Cursor-Out	[^] C [^] O
Oplevel-Cursor-Out	Up-Arrow
Previous-Line	Cursor-Out at level "Character"
Previous-Line	Cursor-Out at level "Word"
Previous-Line	Cursor-Out at level "Line"

The cursor can also be moved using cursor motion commands shown above. If the operand level were "Word", then *Oplevel-Cursor-Forward* would move the cursor to the word following the word containing the cursor and *Oplevel-Cursor-To-First* would move the cursor to the first word in the view. The "Next-" and "Previous-" commands use the numeric prefix argument to determine the number of units to move.

Note that the generic commands *Cursor-In* and *Cursor-Out* (bound by default to "Down-Arrow" and "Up-Arrow" respectively) have little meaning for ordinary textual editing. They are bound to *Next-Line* and *Previous-Line* respectively at all three textual operand levels.

Moving Around in the Text Stream

Oplevel-Cursor-To-First	[^] C Esc <
Move-To-Bos	Esc <
Move-To-Bos	Cursor-To-First at level "Character"
Move-To-First-Word	Cursor-To-First at level "Word"
Move-To-Bos	Cursor-To-First at level "Line"
Oplevel-Cursor-To-Last	[^] C Esc >

Move-To-Eos	Esc >
Move-To-Eos	Cursor-To-Last at level "Character"
Move-To-Last-Word	Cursor-To-Last at level "Word"
Move-To-Last-Line	Cursor-To-Last at level "Line"
Move-To-Bol	^A
Move-To-Eol	^E
End-Of-Word	Not bound
First-Non-Blank	Esc m
Goto-Line	^X 1

Move-To-Bol moves the cursor to the first position on the current line; **Move-To-Eol** moves the cursor to the last position on the current line. To move to the beginning or end of the view being edited, use **Move-To-Bos** or **Move-To-Eos**, respectively.

End-Of-Word moves the cursor to the end of the word that encloses the cursor. Finally, **First-Non-Blank** moves the cursor to the first character (that is not white space) on the current line.

The command **Goto-Line** moves the cursor to the beginning of the line specified by the numeric prefix argument. If there is no prefix argument, **Goto-Line** prompts for a line number. Internally, *Pan* treats the first line of a file as line number 0. If the option **Zero-Index-Lines** is false, the argument to **Goto-Line** is treated as a 1-indexed line number and is converted appropriately.

Mark Commands

Set-Mark	^@
Pop-Mark	Not bound
Push-Mark	Not bound
Swap-Dot-And-Mark	^X ^X
Dot-To-Mark	Not bound

Set-Mark and **Push-Mark** both push the location of the cursor to the top of the mark stack of the active view. **Pop-Mark** pops the mark stack of the active view. The commands **Swap-Dot-And-Mark** and **Dot-To-Mark** move the text cursor to the position indicated by the top of the mark stack. They differ in that the first exchanges the cursor's position with the top mark, while the second pops stack.

4.2 The Current Operand Level

Set-Oplevel-To-Character	^C c
Set-Oplevel-To-Word	^C w
Set-Oplevel-To-Line	^C l

The current operand level is a *mode* which affects the subsequent operation of operand level commands (a.k.a. level-sensitive commands), see Section 4.3. The level does *not* affect the operation

of any other commands: in particular, text may be entered and manipulated freely, independent of level.

The operand level may be set by using these commands or selected using “Mouse-Right” over the menu in the information panel where the current level is always visible. You can leave the operand level at “Character”, and *Pan* will operate much like *Emacs*.

Other operand levels related to languages are described in Section 6.4.

4.3 Operand Level Commands

Oplevel-Cursor-Forward	<code>^C ^F</code>
Oplevel-Cursor-Forward	Right-Arrow
Oplevel-Cursor-Backward	<code>^C ^B</code>
Oplevel-Cursor-Backward	Left-Arrow
Oplevel-Cursor-In	<code>^C ^I</code>
Oplevel-Cursor-In	Down-Arrow
Oplevel-Cursor-Out	<code>^C ^D</code>
Oplevel-Cursor-Out	Up-Arrow
Oplevel-Cursor-To-First	<code>^C Esc <</code>
Oplevel-Cursor-To-Last	<code>^C Esc ></code>
Oplevel-Cursor-To-Mouse	<code>^C Mouse-Left</code>
Oplevel-Select	<code>^C Backspace</code>
Oplevel-Mouse-Extend	<code>^C Mouse-Middle</code>
Oplevel-Delete	<code>^C ^D</code>
Oplevel-Cursor-Search-Forward	<code>^C ^S</code>
Oplevel-Cursor-Search-Forward	L9
Oplevel-Cursor-Search-Backward	<code>^C ^R</code>
Oplevel-Replace-All	<code>^C Esc r</code>
Oplevel-Query-Replace-All	<code>^C Esc ^R</code>
Oplevel-Menu	<code>^C Mouse-Right</code>

These are generic commands whose behavior depends on the current operand level and on operand level bindings (both command and menu). They may be bound to different commands at any operand level in any given scope. Note that the key bindings for these commands are the same as the key bindings for the analogous character level commands prefixed by the key sequence “`^C`”.

The first five commands control cursor movement relative to the operand level; see Section 4.1 for more detail. *Oplevel-Select* selects the operand under the edit cursor. *Oplevel-Mouse-Extend* extends the selection to include the mouse position; see Section 4.4. *Oplevel-Delete* deletes the operand under the edit cursor. The “Search” and “Replace” commands are discussed in Section 4.13.

The operand level menu is specific to each particular operand level and usually contains all of the commands which are bound to the generic commands by default at that operand level.

4.4 The Textual Selection

Oplevel-Cursor-To-Mouse	<code>^C Mouse-Left</code>
Oplevel-Mouse-Extend	<code>^C Mouse-Middle</code>
Oplevel-Select	Not bound
Cursor-To-Mouse	<code>Mouse-Left</code>
Select-Region-Dot-To-Mark	<code>Esc ^W</code>
Select-Region-Dot-To-Mouse	<code>Mouse-Middle</code>
Select-Region-Dot-To-Mouse	<code>Mouse-Extend at level "Character"</code>
Select-Word	<code>Esc @</code>
Select-Line	<code>Select at level "Line"</code>
Select-Fullword	<code>Select at level "Word"</code>
Select-Full-Line	Not bound
Select-Text-Stream	<code>^X h</code>
Mouse-Select-Word	Not bound
Mouse-Select-Line	<code>Cursor-To-Mouse at level "Line"</code>
Mouse-Select-Fullword	<code>Cursor-To-Mouse at level "Word"</code>
Mouse-Select-Fullword	<code>Esc Mouse-Left</code>
Mouse-Select-Full-Line	Not bound
Mouse-Extend-Selection-Fullword	<code>Esc Mouse-Middle</code>
Mouse-Extend-Selection-Full-Line	Not bound
Mouse-Extend-Oplevel-Text	<code>Mouse-Extend at level "Word"</code>
Mouse-Extend-Oplevel-Text	<code>Mouse-Extend at level "Line"</code>
Next-Line-Select	Not bound
Previous-Line-Select	Not bound
Select-Expr	<code>Esc ^@</code>
Null-Select	Not bound
Deselect-Region	<code>Select at level "Character"</code>
Deselect-Region	<code>Esc ^D</code>

Each textual view has a single textual selection, shared by all windows. It may be set in any window, but it is visible in all windows. Any alteration of the text stream deselects the textual selection. The text selection is generally set by the commands `Select-Region-Dot-To-Mouse`, `Oplevel-Cursor-To-Mouse`, `Oplevel-Mouse-Extend`, and `Select-Region-Dot-To-Mark`. `Select-Region-Dot-To-Mouse` is bound to `"Mouse-Middle"` and selects the region between the text cursor and the mouse. `Oplevel-Cursor-To-Mouse` is bound to the key sequence `"^C Mouse-Left"` and selects one unit at the current operand level beneath the mouse cursor. `Oplevel-Mouse-Extend` is normally bound to the key sequence `"^C Mouse-Middle"`. When the level is `"Character"`, this command selects the region between the text cursor and the mouse. At other levels, it selects the region that *includes* both the current selection and the operand (relative to the current operand level) beneath the mouse cursor. `Select-Region-Dot-To-Mark` selects the implicit region between the top mark on the mark stack and the text cursor.

“-Fullword” commands select the entire word back to the first letter. Likewise, “-Full-Line” commands select the entire line from the first character in the line.

The command **Select-Word** selects the region from the text cursor to the end of the word surrounding the text cursor, while **Mouse-Select-Fullword** selects the full word beneath the mouse cursor. **Mouse-Extend-Selection-Fullword** extends the text selection to include the full word beneath the mouse cursor. **Select-Text-Stream** selects all the text in the view.

When the cursor is positioned on a left brace, bracket, or parenthesis, **Select-Expr** selects the region from that character to the matching right brace, bracket, or parenthesis.

Null-Select creates a selection with one blank at the cursor.

The commands **Select-Line** and **Select-Full-Line** consult the numeric prefix and select that number of lines. The commands **Next-Line-Select** and **Previous-Line-Select** also consult the numeric prefix and move that number of lines forward or backward before selecting one line.

The current selection can be cleared using **Deselect-Region**.

4.5 Entering Text

Self-Insert	most printable characters
Quote-Character	~Q
Newline-And-Indent	LineFeed
Insert-Newline	Return
Indent-Like-Previous-Line	Esc Tab
Center-Line	Not bound
Open-Line	~0
Split-Line	Esc ~0
Insert-Parentheses	Esc (
Insert-File	~X Tab
Insert-File	Text Edit⇒File: Insert Text from...

Typing a printable character generally causes that character to be inserted into the text at the position of the cursor. When printable characters are typed consecutively, the **Self-Insert** commands are merged into a single action for the purpose of **Undo** operations. **Quote-Insert** inserts the next ASCII character typed even if it is a control character.

Newline-And-Indent is bound to the “**LineFeed**” character; the next line will be indented to the level of the previous line by inserting tabs and blanks. **Center-Line** centers the current line between the beginning of the line and the value of the **Text-Line-Length**. **Indent-Like-Previous-Line** simply reindents the current line to the level of the previous line.

Open-Line inserts “**newline**” characters after the cursor; the number of “**newline**” characters inserted is determined by the value of the numeric prefix argument (default 1). **Split-Line** does the same thing, but also indents any text following the cursor to its original horizontal position.

The command **Insert-Parentheses** inserts a pair of matching parentheses at the cursor, and positions the cursor between them.

Insert-File prompts for a file name and copies the contents that file into the active view at the position of the text cursor.

4.6 Filling Text

Set-Text-Line-Length	<code>^X f</code>
Toggle-Text-Fill	<code>^X ^A</code>
Insert-Space-Fill	Space
Insert-Newline-Fill	Return
Fill-Selected-Lines	Not bound
Set-Text-Fill-Prefix	<code>^X .</code>
Text-Fill-To-Blank-Line	Esc q

To **fill** text means to move text from line to line so that all the lines are approximately the same length. *Pan* has a rudimentary mechanism for filling text lines as you type them. When the **Text-Fill** option is on, the flag “`☞`” appears in the information panel and the keys “**Space**” and “**Return**” are bound to special procedures. These procedures compare the current horizontal position of the cursor with the value of **Text-Line-Length**. If the line is too long, it will be broken where appropriate; if not, the procedures act like **Self-Insert**. Use **Toggle-Text-Fill** to turn on text filling and again to turn it back off. When filling is on, you can type text continuously without worrying about line length.

Use **Set-Text-Line-Length** (with a numeric prefix argument) to set the maximum line length used by auto-filling.

The commands **Fill-Selected-Lines** and **Text-Fill-To-Blank-Line** fill more than one line at a time. The first fills the selection; the second fills all lines from the cursor to the first blank line following the cursor.

Set-Text-Fill-Prefix sets the line prefix to the characters before the cursor on the line with the cursor. This prefix is then added to the beginning of each new line as it is started. This is useful for indenting an entire section of text or for prefixing each line with a fixed string of characters.

4.7 Deleting Text

Oplevel-Delete	<code>^C ^D</code>
Delete-Character	<code>^D</code>
Delete-Character	Delete at level “Character”
Delete-Previous-Character	Delete
Delete-Previous-Character	Backspace
Delete-Word	Delete at level “Word”
Delete-Fullword	Not bound
Delete-Previous-Word	Not bound
Delete-Line	Delete at level “Line”
Delete-Selected-Region	Not bound
Delete-Region-Dot-To-Mark	Not bound
Delete-Blank-Lines	<code>^X ^O</code>
Delete-Horizontal-Space	Esc \
Just-One-Space	Esc Space
Delete-Indentation	Esc ^

Deleted text can be recovered by issuing an “Undo” command immediately after the deletions, but in no other way. Deleted text is *not* retained in the kill ring. The standard bindings reflect this limitation by using “Kill” commands when removing large regions. *Pan* merges deletions that are contiguous in space and time into a single undo-able action.

Oplevel-Delete deletes one unit at the current operand level. Thus, if the operand level is “Character”. **Oplevel-Delete** deletes one character. **Delete-Character** deletes the character under the cursor. **Delete-Previous-Character** deletes the character before the cursor. The pair of commands **Delete-Word** and **Delete-Previous-Word** delete from the cursor to the end (beginning) of the word enclosing the cursor, while **Delete-Fullword** deletes the entire word enclosing the cursor. The commands **Delete-Selected-Region** and **Delete-Region-Dot-To-Mark** operate on the selection and the implicit selection, respectively.

There are several ways to delete white space around the cursor. **Delete-Blank-Lines** deletes vertical and horizontal white space, leaving exactly one blank line at the cursor. **Delete-Horizontal-Space** deletes white space surrounding the cursor on the same line as the cursor. **Just-One-Space** does the same thing, but leaves exactly one space at the cursor. **Delete-Indentation** removes any leading white space on the line containing the cursor.

4.8 Killing Text

Kill-Word	Esc d
Kill-Previous-Word	Esc Del
Kill-To-Eol	^K
Kill-Expr	Esc ^K
Kill-Selected-Region	^W
Kill-Selected-Region	Text Edit: Kill
Kill-Region-Dot-To-Mark	Not bound
Copy-Selection-As-Kill	Esc w
Yank-From-Kill-Ring	^Y
Yank-From-Kill-Ring	Text Edit: Yank
Cycle-Yank	Esc y
Cycle-Kill	Not bound
Show-Kill	^X ?
Cycle-Show-Kill	^X !

Like the deletion commands of the previous section, commands that kill text remove the text from a view. Unlike deletion commands, however, these also copy the removed text into the kill ring.

The pair of commands **Kill-Word** and **Kill-Previous-Word** kill from the cursor to the end (beginning) of the word enclosing the cursor. The command **Kill-Expr** kills the text of the next word or of the balanced bracket expression following the text cursor. The commands **Kill-Selected-Region** and **Kill-Region-Dot-To-Mark** kill the current textual selection and the implicit selection, respectively. **Kill-To-Eol** kills all characters up to the end of the line.

Text in the kill ring can be recovered using the command **Yank-From-Kill-Ring** which copies the contents of the top item in the kill ring into the view at the current cursor position. If a prefix argument is present, then **Yank-From-Kill-Ring** will *replace* the current selection with the copied item.

Cycle-Yank cycles the kill ring (see Section 2.4) before yanking the top of the kill ring. **Copy-Selection-As-Kill** copies the current selection to the kill ring without removing it from the text stream.

The command **Show-Kill** displays the first item in the kill ring. The commands **Cycle-Kill** and **Cycle-Show-Kill** both cycle the kill ring; **Cycle-Show-Kill** also shows the new top item.

The maximum number of items stored in the kill ring is determined by the option **Killring-Max-Size**. If the option **Kills-To-Clipboard** is set then all kill commands use the global clipboard instead of the view-specific kill rings.

4.9 The Clipboard

Cut-To-Clipboard	Clipboard: Cut
Cut-To-Clipboard	L10
Copy-To-Clipboard	Clipboard: Copy
Copy-To-Clipboard	L6
Paste-From-Clipboard	Clipboard: Paste
Paste-From-Clipboard	L8
Replace-From-Clipboard	Not bound
Cycle-Clipboard	Not bound
Show-Clipboard	Clipboard: Show Contents
Show-Clipboard	Esc ?
Cycle-Paste	Not bound
Cycle-Show-Clipboard	Clipboard: Cycle and Show
Cycle-Show-Clipboard	Esc !

These commands manipulate the contents of the global clipboard shared by all views. **Cut-To-Clipboard** deletes the current textual selection and places it onto the clipboard. **Copy-To-Clipboard** places a copy of the current selection onto the clipboard. **Paste-From-Clipboard** inserts a copy of the top item of the clipboard at the text cursor. If a prefix argument is present, then **Paste-From-Clipboard** will *replace* the current selection with the top item of the clipboard. Finally, **Replace-From-Clipboard** replaces the selected region with the top item of the clipboard.

The command **Show-Clipboard** displays the first item of the clipboard in the help view. **Cycle-Clipboard** cycles the clipboard using the prefix argument to determine the number of entries to move, while **Cycle-Show-Clipboard** combines the two actions. **Cycle-Paste-Clipboard** cycles the clipboard and pastes the new top element into the text stream at the cursor.

The maximum number of items in the clipboard is determined by the option **Clipboard-Max-Size**.

4.10 Copying and Moving Text

Copy-Selection-To-Cursor	Esc ^Y
--------------------------	--------

Copy-Selection-To-Cursor	Text Edit: Copy To Cursor
Move-Selection-To-Cursor	Esc Return
Move-Selection-To-Cursor	Text Edit: Move To Cursor

Text can copied or moved within a textual view by using either the clipboard or the local kill ring. However, the above commands are useful short cuts. Both use the current selection as the source to copy or move, and the text cursor to mark the destination. These commands operate only within a view; copying and moving between views requires the clipboard.

4.11 Changing Case

Capitalize-Word	Esc c
Lowercase-Word	Esc l
Uppercase-Word	Esc u
Capitalize-Selection	Esc ^C
Lowercase-Selection	Esc ^L
Uppercase-Selection	Esc ^U

These commands are use to change cases within a word or region. The word-oriented commands operate on the region from the cursor to the end of the word and leave the cursor at the end of the word when done. The selection-oriented commands leave the cursor at the beginning of the affected selection.

4.12 Transposing Text

Transpose-Characters	^T
Transpose-Characters-At-Cursor	Not bound
Transpose-Lines	^X ^T

Transpose-Characters exchanges the character at the cursor and the character before the cursor unless the cursor is at the end of a line, in which case it transposes the previous two characters. **Transpose-Characters-At-Cursor** the character at the cursor and the character before the cursor even if the cursor is at the end of a line. **Transpose-Lines** exchanges the line containing the cursor with the line before it.

4.13 Searching Text

Pan provides commands for searching for regular expressions and for matching balanced brackets.

Regular Expressions

Oplevel-Cursor-Search-Forward	L9
Oplevel-Cursor-Search-Forward	^C ^S
Re-Search-Forward	^S

Re-Search-Forward	Cursor-Search-Forward at level "Character"
Re-Search-Forward	Cursor-Search-Forward at level "Line"
Oplevel-Cursor-Search-Backward	^C ^R
Re-Search-Backward	^R
Re-Search-Backward	Cursor-Search-Backward at level "Character"
Re-Search-Backward	Cursor-Search-Backward at level "Line"
Oplevel-Query-Replace-All	^C Esc ^R
Query-Replace-All	Esc ^R
Query-Replace-All	Query-Replace-All at level "Character"
Query-Replace-All	Query-Replace-All at level "Line"
Oplevel-Replace-All	^C Esc r
Replace-All	Esc r
Replace-All	Replace-All at level "Character"
Replace-All	Replace-All at level "Line"

These commands prompt for an expression argument and then search for text matching the standard UNIX regular expressions. For a description of those expressions, see the ED(1) manual page of the UNIX Programmer's Manuals. *Pan* is unable to search for patterns which contain embedded "newline" characters. The most recently specified regular expression is shared by all views.

The "Oplevel-Cursor-Search" and "Oplevel-Replace" commands step through each unit at the given level and try to match the argument pattern to the given unit. This has more meaning when you are using the operand levels associated with a programming language (see Section 6.4). When you are using a program operand level, the pattern must match the entire operand unless a numeric prefix is present, in which case it may match a subset of the operand. The "Character" and "Word" levels allow the pattern match to span more than one operand. When text matching a pattern is found, the text cursor is moved to the first character in the match, and the matched text is selected.

Both **Re-Search-Forward** and **Re-Search-Backward**, the text level search commands, process the numeric prefix argument idiosyncratically: the *presence* of a prefix argument causes the command to search using the last regular expression specified. For instance, "**^U ^S**" invokes **Re-Search-Forward** using the most recent search pattern—and the command will match the *next* occurrence of the pattern. Alternatively, supplying an empty string as the regular expression causes the previously specified expression to be used.

When the option **Autowrap-Search** is true, searches wrap from one end of the view to the other; if that option is false, searches terminate when finding the beginning or end of the view.

The "**Replace**" commands search for a string and replace all instances of it with the specified replacement string. **Oplevel-Query-Replace-All** asks the user whether to replace, ignore, or cancel the search at each instance of the sample string.

The set of replacements made during a "**Replace**" command are grouped together as a single action for the purpose of "Undo" operations. However, the **Sub-Undo** command allows you to undo the individual replacements one at a time (see Section 3.7).

Balanced Bracket Commands

Backward-Expr	Esc ^B
Forward-Expr	Esc ^F
Select-Expr	Esc ^@
Kill-Expr	Esc ^K
Show-Match	Esc %

These commands use character set definitions to operate on balanced bracket expressions. The set `match-characters` contains all of the characters which are defined to have matches. Both `Forward-Expr` and `Backward-Expr` move the cursor. The `Select-Expr` command selects the balanced bracket expression surrounding the cursor, and the command `Kill-Expr` kills it.

If the cursor character is in the set `match-characters`, `Show-Match` moves the cursor to the matching bracket, pauses for the value of the option `Pause-Ticks` internal ticks, and returns the cursor to its original position. If the option `Auto-Show-Match` is set then `Show-Match` is called every time a right bracket from the `match-characters` set is typed.

5 Using Graphical Views

Zoom-In	i
Zoom-In	“in” button in control panel
Zoom-In	Window: Zoom In
Zoom-Out	o
Zoom-Out	“out” button in control panel
Zoom-Out	Window: Zoom Out
Zoom-Reset	a
Zoom-Reset	“all” button in control panel
Zoom-Reset	Window: Zoom All
Global-Image-Toggle	g
Global-Image-Toggle	Window: Toggle Global Image
Global-Image-Enlarge	e
Global-Image-Enlarge	Window: Enlarge Global Image
Global-Image-Shrink	s
Global-Image-Shrink	Window: Shrink Global Image

A graphical view can be created to represent the internal tree representation of a program or other structure-based view. The textual label on the graph nodes vary depending on which command was used to generate the view. This view functions only as a display and can not be used to alter the contents of the textual view from which it was generated. Other graphical views are anticipated, but not yet implemented.

Currently, the graphical views can be navigated only by zooming in and out via the commands `Zoom-In` and `Zoom-Out`, which are bound to the in and out buttons on the control panel, and scrolling with the scroll bars on the window frame. The `Zoom-` commands scale the view up or down by a factor of `Graph-Window-Zoom-Factor` (whose default value is 0.1). The “Zoom-”

commands take a numeric prefix and effectively zoom in or out that many times to produce more drastic scale changes. Only the middle button of the mouse functions for scrolling in a graph view. The left and middle buttons of the mouse have no effect when the mouse is over the display area, but the right button still invokes a menu.

The global image shows the entire graph being viewed and marks the portion of the graph which is visible in the window. It appears in the upper left corner of the graph view window. It may be resized using *Global-Image-Enlarge* and *Global-Image-Shrink* and it may be toggled on and off using the command *Global-Image-Toggle*.

6 Language-Oriented Services

In addition to its more conventional text-based services, *Pan* provides facilities for viewing and modifying textual objects whose underlying structure can be described by formal languages, for example programs. These services require the loading of one or more *Pan* language descriptions, as discussed in sections 2.7 and 7.1. In no case, however, does the presence of a language description inhibit the operation of *Pan*'s text facilities; users need incur no loss of convenience to benefit from *Pan*'s more advanced features.

The basic interface provided by *Pan* for language-oriented editing is uniform across languages. It is also configured specially for each language and can be customized further for any particular language and for any style of interaction. Finding an appropriate balance between uniformity and specialization is encouraged by *Pan*'s configuration mechanisms, but by no means assured. This is a matter of user interface design on the part of the author of *Pan*'s language descriptions, and is the subject of ongoing research.

This section introduces *Pan*'s basic language-oriented editing features. Many of these are experimental, and more are under development. A more thorough discussion of these features appears elsewhere [8].

All interaction with a program takes place in the context of a view on that program, where both textual and graphical views are supported in the current implementation. It is intended, however, that ordinary programming take place in the context of a primary textual view, a view that operates very much like an ordinary text editor but with many extra language-based services available.

Pan's basic language-oriented services include a number of program views that will be of primary interest to system extenders and especially to authors of language descriptions. see Section 6.12. For example, different tree views can be created which contain subtrees of the entire structure or which display different information at the tree nodes. Views can also be created which display information about the lexical stream or the semantic database. These alternate views are usually updated every time the program is reanalyzed.

Ladle syntax descriptions have been written for Modula-2[9], Pascal, Ada, *Ladle*, *Colander*, and ASPLE[4]. ASPLE is a simple example language used for demonstrations and for learning *Pan*. Other language descriptions, including *C*, *C++*, and FIDIL[6], are under development. A *Colander* semantic description has been written for Modula-2, as well as some small demonstration languages, including TINY and SIMPLE. SIMPLE2 is a second language description for the language SIMPLE which provides additional and somewhat different services to the user.

Figure 3 shows a *Pan* session involving two views on a SIMPLE2 program: one textual and one graphical.




Figure 3: Two language-based views on a program

In contrast to earlier examples, the “Language:” field in the information panel now reads “SIMPLE2”, revealing that the language description has been loaded and is being used for this view. The default menu has been augmented; new submenus **Language** and **Variables** appear and the **View** menu contains additional submenus **Program Graph** and **Subgraph At Cursor**. The **Variables** menu provides access to commands which allow you to query or rename a variable or to visit its definition, while the additional **View** menus provide quick access to the graphical language-based views. As with text views, many of these commands are also available from the keyboard.

6.1 Language-Based Textual Views

Most user interaction with programs takes place in the context of what appears at first glance to be an ordinary *Pan* textual view, for example the view whose window appears at the upper left of Figure 3 on page 35. In fact, all of the conventional text-based support provided by *Pan* continues to be available at all times with no restrictions. The language-based information derived by *Pan*’s analyzers is kept behind the scenes. The information is used to support a variety of user services, but

only when those services are requested. Whenever structural information is required for execution of a command, incremental syntactic analysis (parsing) updates the internal tree structure. Most of the time, this transformation is hidden from the user — it occurs automatically as operations like “delete the selected subtree” are invoked. Whenever possible, the language-based services provided by *Pan* are similar in form, name, and default key binding to analogous text operations.

The information panel in windows owned by language-based views differs slightly from those for purely text-based views. For example, the name of the language description being used appears in place of “Text” in the “Language:” field.

Two additional flags reveal the presence and status of derived information:

- The “^” (**Parse-Is-Current?**) flag is visible, but gray, when there are textual changes that have not yet been incorporated into the tree by the syntactic analyzer, that is when the tree is present but inconsistent with the text. The flag appears solid when text and structure are consistent.
- The “D” (**Database-Updated?**) flag is visible, but gray, when there are changes that have not yet been incorporated into the semantic database. This flag is absent entirely when there is no *Colander* component to the language description being used. The flag appears solid when the database is consistent with text and structural information.

Pan’s default behavior at present for language errors (that is, for situations where a program violates part of the language’s definition) is to show the user two categories of error, reflecting *Pan*’s underlying implementation. In the default configuration two additional flags reveal the presence of language errors:

- The “!” (**Syntax-Errors-Present?**) flag appears when there are lexical or syntactic errors in the program being edited.
- The “#” (**Semantic-Errors-Present?**) flag appears when there are semantic errors in the program being edited.

It is possible, however, to configure a language description so that the user only sees one category of error in place of the two. Section 6.8 discusses this topic in more detail.

6.2 Language-Based Analysis

Analyze-Changes	Language: Analyze
Analyze-Changes	^C a
Visit-And-Check-File	Not bound

Language-based analysis is the process of deriving information from text based on an underlying description of the structure of the language, a set of contextual constraints, and possibly other information.

The analysis method used is incremental—only the areas affected by the changes are reanalyzed. Analysis occurs whenever the derived information is out of date with respect to the text and when a language-oriented operation takes place, for example when the user invokes a tree-oriented

navigation command. Analysis can also be invoked explicitly, with the command **Analyze-Changes**. This command is also used internally to invoke analysis if there have been any changes in the contents of the view. **Visit-And-Check-File** performs the same function as **Visit-File** but also analyzes the view's contents.

Syntactic analysis incorporates changes in a view's contents into the tree that represents a program. Syntactic analysis is a two-stage process. In the first stage, the text stream is broken into larger fragments called **lexemes**. Lexemes are the basic symbols in the language being edited, e.g., keywords, identifiers, constants, and comments.

When a view is lexically analyzed, various classes of lexemes are given different visual images using fonts. The following table defines the relationship between font codes and characters in lexemes. These codes permit the assignment of specific fonts (via the font map mechanism, see Section 7.5) to each category for each language⁵.

Class	Example	Font
Unanalyzed characters	inserted text	0
Ignored by the lexical analyzer		1
Fixed-length lexemes	keywords	2
Recognized but not analyzed	comments	3
Variable-length lexemes	identifiers	4

Semantic analysis checks a program against a set of contextual constraints defined in the *Colander* component of the language description. These constraints may be based on the language definition, for example type checking, on the intended use, for example naming conventions, and many other restrictions as needed. At the same time, semantic analysis records facts about the program in the semantic database that are used to support various services.

6.3 Consistency and Inconsistency

Unlike syntax directed editors, which don't permit you make a mistake or restrict your options when you do, *Pan* allows the text to be modified without restriction at all times. When text has been changed since last analysis, the derived information is said to be **inconsistent**: it should be considered unreliable and may be incomplete. In this situation, the **Parse-Is-Current?** and **Database-Updated?** flags appear gray and newly entered unanalyzed text is displayed using the default font 0. Any text which has previously been analyzed and assigned a non-default font remains in that font until it is reanalyzed. Also any text which has been highlighted as a syntactic or semantic error remains highlighted until it is reanalyzed. When derived information becomes inconsistent, the structure cursor is cleared (see Section 6.5).

Pan's current implementation requires consistency for any structural operation. Therefore, reanalysis takes place whenever any structural information is needed. Work is underway to loosen this restriction.

Note that derived information may be consistent or inconsistent whether or not there are language errors (*Pan* separates the two), see Section 6.8.

⁵No single combination of font assignments seems to be best for all languages. Designing a font map is part of the user interface design work for the author of a *Pan* language description.

6.4 Operand Levels

Set-Oplevel-To-Lexeme	<code>^C x</code>
Set-Oplevel-To-Syntactic-Error	<code>^C !</code>
Set-Oplevel-To-Semantic-Error	<code>^C #</code>
Set-Oplevel-To-Query	<code>^C q</code>
Set-Oplevel-To-Node	Not bound
Oplevel-Menu	<code>^C Mouse-Right</code>

Unlike simple textual views in which only the three textual operand levels are available, the list of operand levels available in a language-based text view is part of *Pan*'s configuration for the particular language, defined by **Operand-Level-Choices**. This list defines what components of a program (more accurately, of *Pan*'s representation of a program) that the user "sees" and can manipulate.

Some of the operand levels are standard across all languages, for example the three textual levels and the lexical level. Some levels have the same or similar names as analogous levels in other languages (e.g. statement, expression), but their internal definitions differ according to the underlying language description.

These are the operand levels for the example language, **SIMPLE2**: "Lexeme", "Expression", "Statement", "Declaration", "Placeholder", "Syntactic Error", "Unsatisfied Constraint", and "Query". Figure 4 on page 39 shows the set of operand levels defined for **SIMPLE2**.

All of the previously defined **Oplevel** commands may have bindings at these levels. Thus cursor motion, selection, deletion, and searches may all be effected relative to the structure of the program. The operand levels for a language are related to nodes in the *Ladle* description of the language. They must be specified in the language-mode file which is loaded in and executed when a view in that language is edited. (See **Auto-Load** and **Auto-Exec** in Section 7.1) To see the available operand levels for a language, simply inspect the panel "Level:" menu. There are also key bindings designed to permit level selection from the keyboard: standard bindings for the standard levels, language-specific ones for the language-specific levels.

There are menus available for each level, executable by the command **Oplevel-Menu**, which make available many of the same generic commands that have key bindings. In some cases, the level-specific menus may be extended in ways specific to each language.

The command **Set-Oplevel-To-Node** is used for debugging. It sets the operand level to all nodes of the internal tree, whereas most operand levels define useful subsets of the internal tree. Note however that this command, like all **Set-Oplevel-** commands, works only if the specified level is permitted in the view, as controlled by option **Operand-Level-Choices**.

6.5 The Structure Cursor

Clear-Structure-Cursor	<code>Esc ^D</code>
Cursor-To-Token	Not bound
Announce-Structure-Cursor-Info	<code>^C ^X =</code>
Announce-Structure-Cursor-Node-Rule	Not bound




Figure 4: The operand levels for SIMPLE2

The **structure cursor** is a reference to one component in the internal tree representation of a structured object; it is shared by all views on a program. At any point the structure cursor may or may not be present. Currently, the structure cursor is only usable when the derived information is consistent with the text. When an operand level command is invoked and the operand level corresponds to a program structure type (such as “Lexeme” or “Expression”), the structure cursor is set to the current node at that operand level. Commands which operate on a structure node, such as “Visit-Program-Subgraph-” commands, take the structure cursor’s node as their argument.

Whenever the structure cursor is set, the textual selection will also be set to the region of text which corresponds to the structure cursor and the text cursor in the active window will be moved to the beginning of that region.⁶ If the option **Highlight-Structure-Cursor** is set, then the region of text in the program which corresponds to the structure cursor will be visible as a light blue highlighted region. The highlight color for the structure cursor may be set to any color by setting the option **Text-Window-Bg-Colormap** in the appropriate view (see Section 7.5). The text cursor

⁶Setting or clearing the text selection explicitly clears the structure cursor as a side effect.

may be moved away from the structure cursor without clearing it, but any alterations to the text stream render the derived information inconsistent and clear the structure cursor.

In some cases at certain operand levels (this is configurable), an announcement may accompany positioning the structural navigation at a node, for example error diagnostics (see Section 6.8)

Clear-Structure-Cursor clears the structure cursor without clearing the textual selection. **Cursor-To-Token** sets the cursor to be the token which contains the text cursor regardless of the current operand level. **Announce-Structure-Cursor-Info** displays information about the node at the structure cursor in the information panel. **Announce-Structure-Cursor-Node-Rule** displays information in the information panel about the reduction rule in the language for the node at the structure cursor (generally used for debugging).

6.6 Setting The Structure Cursor

Oplevel-Cursor-To-Mouse	[^] C Mouse-Left
Oplevel-Mouse-Extend	[^] C Mouse-Middle
Oplevel-Select	[^] C Backspace
Mouse-Select-Lexeme	Cursor-To-Mouse at level "Lexeme"
Mouse-Select-Oplevel-Node	Cursor-To-Mouse at level "Any Structure Level"
Mouse-Extend-Lexeme	Mouse-Extend at level "Lexeme"
Mouse-Extend-Oplevel-Node	Mouse-Extend at level "Any Structure Level"
Select-Lexeme	Select at level "Lexeme"
Select-Oplevel-Node	Select at level "Any Structure Level"

Selection during language-oriented editing relies on the notion of operand levels (section 2.6). In a language-oriented view, the set of operand levels is much richer than in the text world. The operand levels for text editing are included, as well as levels corresponding to basic abstractions in the language being edited (see Section 6.4).

As with text, the command **Oplevel-Cursor-To-Mouse**, bound to [^]C Mouse-Left, selects the operand beneath the mouse cursor. The structure node which will be designated by the structure cursor and the region of text actually chosen are determined by the operand level. Thus if the mouse cursor is over the character "*" in Figure 4 on page 39 when the left button is clicked, the selected object might be the underlying lexeme "*", expression "outerI * valueI", or statement "countI := outerI * valueI + resultI" depending on whether the operand level is "Lexeme", "Expression", or "Statement" respectively.

What happens if the object beneath the mouse cursor is not an element of the class of objects specified by the current operand level? Then *Pan* uses a heuristic to find an object close to the mouse cursor that is an element of that class. This behavior is fairly predictable, although in some cases it leads to unforeseen selections.

To select arbitrary portions of a structure, use the "Character" level commands and operate on the textual representation.

6.7 Structural Navigation

Oplevel-Cursor-Forward	[^] C [^] F
------------------------	-------------------------------

Oplevel-Cursor-Forward	Right-Arrow
Oplevel-Cursor-Backward	^C ^B
Oplevel-Cursor-Backward	Left-Arrow
Oplevel-Cursor-To-First	^C Esc <
Oplevel-Cursor-To-Last	^C Esc >
Oplevel-Cursor-To-Mouse	^C Mouse-Left
Oplevel-Cursor-In	^C ^I
In-Oplevel-Node	Cursor-In at level "Any Structure Level"
Oplevel-Cursor-Out	^C ^O
Out-Oplevel-Node	Cursor-Out at level "Any Structure Level"
Oplevel-Menu	^C Mouse-Right
Next-Lexeme	Cursor-Forward at level "Lexeme"
Next-Oplevel-Node	Cursor-Forward at level "Node"
Prev-Lexeme	Cursor-Backward at level "Lexeme"
Prev-Oplevel-Node	Cursor-Backward at level "Node"
First-Lexeme	Cursor-To-First at level "Lexeme"
First-Oplevel-Node	Cursor-To-First at level "Node"
Last-Lexeme	Cursor-To-Last at level "Lexeme"
Last-Oplevel-Node	Cursor-To-Last at level "Node"

Structural navigation of a program allows you to move the structure cursor from one node of a given type to another where type is defined in the language description by operand levels. Simple navigation involves the "Oplevel-" operations `Oplevel-Cursor-Forward` and `Oplevel-Cursor-Backward`. They perform preorder and reverse-preorder tree walking operations relative to the current operand level. For example, if the operand level setting is "Expression", the command `Oplevel-Cursor-Forward` moves the structure cursor to the "next" expression node. `Oplevel-In` and `Oplevel-Out` move the structure cursor to the nearest enclosed or enclosing node, again relative to the current operand level. `Oplevel-Cursor-To-First` and `Oplevel-Cursor-To-Last` move the structure cursor to the "first" and "last" instances of the current operand level respectively. `Oplevel-Cursor-To-Mouse` moves the structure cursor to the instance of the operand level which is closest to the position of the mouse.

All of the operand level navigation commands are available from the operand level menu as well. This menu can be invoked by the command `Oplevel-Menu` which is normally bound to the key sequence "`^C Mouse-Right`".

6.8 Language Errors

The operand levels "Syntax Error" and "Unsatisfied Constraint" are preset by default in most language descriptions and are of special significance: they are used to locate errors in a structured document and to move the structure cursor from one error node to another. The standard set of "Oplevel-" commands are bound at the "Syntax Error" and "Unsatisfied Constraint" levels to allow quick and easy navigation between errors. The presence of errors in a program in no way interferes with normal text editing. In *Pan*, the identification and diagnoses of language errors is just another kind of derived information; as much service as possible will be supplied in their presence.

Some language descriptions may combine these two types of language errors into a single operand level or may split different types of syntax errors or different unsatisfied constraints into separate levels. The two operand levels and their corresponding flags described here are used in most of the existing language descriptions.

After lexical analysis, provided that there are no lexical errors, the syntactic analyzer updates the internal structured representation.

The syntactic analyzer checks the structure (or syntax) of the program against the *Ladle* description of the language. If the syntactic analyzer encounters syntactic errors, the number of errors discovered during the analysis is displayed on the annunciator line, and the **Syntax-Errors-Present?** flag is set. This flag appears as a “!” on the information panel. When the syntactic analyzer detects an error, the subtrees involved in the error are gathered into an “error subtree”. Selecting the subtree rooted at an error node causes the error message from the syntactic analyzer to be displayed on the annunciator line. If the option **Highlight-Syntax-Errors** is set then the text associated with the syntax error node will be displayed in red ink. Text colors may be changed by setting the option **Text-Window-Fg-Colormap** (see Section 7.5).

The options that control highlighting and color text rendering for languages are described in Figure 5.

Option	Configured By	Default
Highlight-Syntax-Errors	Ink (foreground color) 1	Red
Highlight-Query-Results	Ink (foreground color) 2	Blue
Highlight-Semantic-Errors	Shading (background color) 1	Pale Red
Highlight-Structure-Cursor	Shading (background color) 2	Pale Blue

Figure 5: The options that control structural highlighting

Figure 3 on page 35 shows the display of a syntax error as well as a graphical view displaying the internal tree structure for the error.

The semantic analyzer checks that the program satisfies a set of contextual constraints, for example type restrictions (based on the underlying language definition) and naming conventions (based on intended usage). If the semantic analyzer detects any semantic errors, the number of errors discovered during the analysis is displayed on the annunciator line, and the **Semantic-Errors-Present?** flag is set. This flag appears as a “#” on the information panel. The semantic errors or unsatisfied constraints are represented as annotations on the internal tree. If the option **Highlight-Semantic-Errors** is set then the text associated with the semantic error node will be highlighted in red ink. The highlight colors may be set to any set of colors by setting the option **Text-Window-Bg-Colormap** in the appropriate view (see Section 7.5).

6.9 Editing

Editing structured views is quite simple in *Pan*. Actual editing is implemented by text operations, but navigation and selection may be optionally driven by language-based information.

All insertions use the text-level commands used for text editing⁷. Deletions are accomplished using either text-level commands, or using the **Oplevel-Delete** command. **Oplevel-Delete** will delete the region of text under the structure cursor at the current operand level. Other editing, using the clipboard and the kill ring, function the same as for text editing.

Undoing edit actions restores the text without restoring the structured representation. Thus undoing currently requires reanalysis.

6.10 Searching in Programs

Lexeme-Search-Forward
Replace-Lexemes
Query-Replace-Lexemes

Cursor-Search-Forward *at level "Lexeme"*
Replace-All *at level "Lexeme"*
Query-Replace-All *at level "Lexeme"*

In addition to ordinary textual search, which is always available along with all textual services, regular expression searching may be applied to structural components and particular operand levels. At the moment this is only implemented at the lexical level.

The search commands apply the match pattern to each lexeme except for comments (which are not regarded as lexemes). If a prefix argument is not present then the entire lexeme must match the pattern. Otherwise, the pattern may match a subset of the lexeme. If the option **Case-Sensitive-Lexeme-Search** is set then the match must be case sensitive.

6.11 Queries

The effect of a query is to mark a set of nodes in the internal tree which have some specified property. For example, in **SIMPLE2** a variable may be queried. When a variable has been queried, the text associated with the tree nodes representing the declaration and all of the uses of that variable is displayed in blue. (Text colors may be changed by setting the option **Text-Window-Fg-Colormap**. See Section 7.5) You may then set the operand level to **"Query"** and navigate among these uses of the variable with the normal operand level commands.

The current prototype implementation of queries insists that object protection be turned on while displaying a query result. This means that you must manually clear a query (by toggling the object protection) before you make further modifications. Work is underway to remove this restriction.

6.12 Debugging Features

These features of *Pan* are not generally useful for programming in *Pan*, but are very useful to designers of *Pan* language descriptions.

⁷The language description **SIMPLE2** includes the a rudimentary prototype for the template-expansion style of syntax directed editing. These operations are also implemented textually, but the fact is somewhat hidden from the user since a newly expanded template is always immediately incrementally analyzed, and thereby promoted into structure

Graphical Views

Visit-Program-Graph-View	View⇒Program Graph: With Node Names
Visit-Program-Subgraph-View	View⇒Subgraph At Cursor: With Node Names
Visit-Program-Graph-Operator-View	View⇒Program Graph: With Operators
Visit-Program-Subgraph-Operator-View	View⇒Subgraph At Cursor: With Operators
Visit-Program-Graph-Address-View	Not bound
Visit-Program-Subgraph-Address-View	Not bound
Visit-Program-Graph-Context-View	Not bound
Visit-Program-Subgraph-Context-View	Not bound
Visit-Program-Graph-Parse-Change-View	Not bound
Visit-Program-Subgraph-Parse-Change-View	Not bound
Visit-Program-Graph-Parse-Status-View	Not bound
Visit-Program-Subgraph-Parse-Status-View	Not bound

The **Visit-Program-Graph-** commands all bring up a graphical representation of the internal tree representation for the program. The **Visit-Program-Subgraph-** commands generate a representation for the subgraph of the internal subtree which is rooted at the currently selected node of the graph. The tree is laid out horizontally, with the root at the left and at every node the first child above the second child which is above the third child, etc.

A graphical view is redrawn after every reanalysis of the structure. Subgraph views are removed if a reanalysis ever causes the associated node to be deleted.

The views created by the different variations of these commands are graphically similar: they differ in the way that a textual label is created for each node. In the simplest version, **Visit-Program-Graph-View**, each node is simply named, but other versions add extra information useful for various kinds of debugging.

The colors and line thicknesses of the graph are configurable options.

Other Language-Oriented Views

Visit-Database-View	Not bound
Visit-Node-Semantics-View	Not bound
Visit-Lexeme-Internal-Data-View	Not bound
Visit-Worklist-View	Not bound
Visit-Tree-Internal-Data-View	Not bound
Visit-Subtree-Internal-Data-View	Not bound

These textual views are primarily useful for debugging *Ladle* and *Colander* language descriptions. They are *not* maintained incrementally during text editing. Instead, the first textual modification after analysis causes the view to be marked dirty. As long as the information in the view is inconsistent with the text of the program, it will be displayed in gray. It is then redrawn the next time there is an analysis to reflect the new information.

These views display the internal data representation for the structure of a program. **Visit-Lexeme-Internal-Data-View** creates a view which displays a description of the lexical stream inter-

nal representation. **Visit-Tree-Internal-Data-View** and **Visit-Subtree-Internal-Data-View** both create a view which continually displays a textual description of the internal tree representation.

These views display information derived from the semantic analyzer. **Visit-Database-View** creates a view which contains the contents of the semantic database. **Visit-Node-Semantics-View** creates a view which continually displays the contents of the semantic database for the tree node of the tree cursor at the time the command is executed. **Visit-Worklist-View** creates a view which displays the semantic worklist (currently unsatisfied constraints).

Exploring the Tree Structure

Tree-Up	Not bound
Tree-Down	unbound
Tree-Left	Not bound
Tree-Right	Not bound

This set of navigation commands for textual language-based views is used for debugging. It includes **Tree-Up**, **Tree-Down**, **Tree-Left**, and **Tree-Right**. These are the usual tree-oriented commands. They function in the text view of the program. From the current node, **Tree-Up** moves the structure cursor to the parent, **Tree-Down** moves it to the leftmost child of the current node, **Tree-Left** and **Tree-Right** move the structure cursor to the appropriate sibling in the tree. These commands can be used to explore the actual tree structure, as opposed to the tree structure imposed by the operand hierarchy mechanism⁸.

7 Simple Customization

Pan can be customized by altering option values and bindings, extended by defining new options, flags, and commands or by introducing new code at hooks or notifiers, and broadened by defining new, formal languages by using the language definition language *Ladle* and the semantic definition language *Colander*. This section provides a brief introduction to the facilities for tailoring and extending the system.

7.1 Start-Up Processing

Load-File	^X ^L
Load-From-Text-Stream	Esc ^X
Load-From-Selection	Esc ^S

At start-up, a run-command file named “**.panrc**” is loaded automatically into *Pan*. The “**.panrc**” file should be a file of COMMON LISP and *Pan* commands located either in your working or your home directory.

⁸One could make the same kind of navigation possible by adding the oplevel “Node” to those available on a view and then using the **Oplevel-Cursor-Forward**, **Oplevel-Cursor-Backward**, **Oplevel-Cursor-In**, and **Oplevel-Cursor-Out** commands.

Pan loads the ".panrc" file using the command **Load-File**. All commands that load files use the search path specified by the option **Editor-File-Search-List**. The default value of the option **Editor-File-Search-List** is set to

```
("." "-" "/usr/local/lib/pan/")
```

Pan can be instructed to automatically load files other than ".panrc". One way is to include **Load-File** directives in the ".panrc" file. Such files will be loaded once at start-up. This method can be used to ensure that a certain selection of libraries will always be loaded. A second way is to use the **Auto-Load** command described in the next section.

```
(Load-File "filename")
```

While running *Pan* you can explicitly load commands from any file with the **Load-File** command which prompts for a file name or from any view in *Pan* with the **Load-From-Text-Stream** or **Load-From-Selection** commands.

Language-Based Configuration

Display-Language-List	Help⇒Pan: Language Descriptions Loaded
Auto-Load <i>file-name regular-expression</i>	
Auto-Exec <i>function-name regular-expression</i>	
Display-Auto-Load	Help⇒Pan: Filename Auto-Load Map
Display-Auto-Exec	Help⇒Pan: Filename Auto-Exec Map

The basic textual views on programs all use the standard **text-edit-view-style**, so language-specific configuration must be done at the view-instance level (the **:view** scope). Typically, this is achieved by using the **Auto-Exec** mechanism. When a file in a given language is opened for editing, an auto-exec function, named **<language>-mode** by default, is executed. These functions and all supporting code are in modules named **"<language>-mode.cl"** by default. Loading one of these modules loads all aspects of the language description needed: *Ladle* description, *Colander* description, editing interface configuration and support. *The Pan Engineering Manual*[5] contains more information about configuration and language-based information in particular.

These modules may be preloaded in a dumped *Pan*, or they will be auto-loaded when needed. To see a list of all of the languages for which a *Ladle* syntactic description or a *Colander* semantic description have been loaded, use the command **Display-Language-List**.

The commands **Display-Auto-Load** and **Display-Auto-Exec** display the list of **Auto-Load** and **Auto-Exec** commands which have been defined. The **Auto-Load** command instructs *Pan* to ensure that a file has been loaded whenever a file whose name matches a given UNIX file expression is created. If the **Auto-Load** is set up properly, then the language mode for a file should be loaded when a view is created for the file. The file is loaded at most once as a result of **Auto-Load**.

For instance, **(Auto-Load "c-mode" "*.hc")** tells the system to load the file "c-mode" the first time that a file whose name matches "*.hc" is edited. The file "c-mode" can be either lisp code or compiled lisp code; if both "c-mode.cl" and a "c-mode.fasl" are found in the same

directory, the most recently modified version is chosen.

Similar to **Auto-Load**, the command **Auto-Exec** instructs *Pan* to execute a given *function* whenever a view having a name that matches a given pattern is created. Taken together, **Auto-Load** and **Auto-Exec** can be used to create minor modes.

A **minor mode** is a collection of commands and bindings useful while editing views of a given type. For instance these commands can be used to create a minor mode for T_EX input:

```
(Auto-Load "tex-mode" "*.tex")
(Auto-Exec 'tex-mode "*.tex")
```

The parameterless function **tex-mode** is defined in the library file "**tex-mode.cl**" to set up a specialized collection of bindings. The file "**tex-mode.cl**" also defines a number of commands useful for manipulating T_EXnical text.

7.2 Using Scopes

With-View-Style-Scope *view-style* (*commands*)

With-View-Scope *view* (*commands*)

With-Buffer-Scope *buffer* (*commands*)

To set options or create bindings within a given scope (other than **:global**), the scope must be specified before the command to set the option or create the binding is executed. The default scope for most bindings is **:global**.

Most commonly, the **:view-style** scope is used for setting non-global defaults. For example, to set up the normal key binding for "f" in the directory editor view-style, **dired-view-style**, you could use this lisp code:

```
(With-View-Style-Scope (view-style dired-view-style)
  (Bind-Key 'Dired-Visit "f" :view-style))
```

The other two "-Scope" macros are not often used. Usually, if you want to make a change within a view, you would make the change from within that view or from within an **Auto-Exec** function, and then you don't need to mention the scope explicitly.

7.3 Packaging

Pan's implementation uses the COMMON LISP package system, so every symbol (in particular every command, function, option, etc.) is defined in some package; almost nothing is defined in the default **user** package.

For convenience, all of *Pan*'s commands, functions, options, etc. are imported automatically into the default **user** package. This means that configuration files (e.g. ".panrc"), which typically are left in the **user** package, need not contain package qualifiers for these names (the qualifiers are optional).

The help system by default does not display the package qualifiers for these names: option `Package-Symbol-Names` requests that the qualifiers be displayed.

7.4 Creating Bindings

Pan provides several configuration mechanisms in the form of bindings. Keystrokes, menu items, and generic commands may all be bound to *Pan* commands. All bindings are scoped, with local bindings taking precedence over global bindings. This section describes how to find out what your current bindings are and how to set up new default bindings with your `“.panrc”` file.

When you **shadow** a binding for an object in a given scope, it effectively removes any binding for that object inherited from an enclosing scope if any such binding exists.

It is possible to invoke a command without binding it by using the commands `Execute-Lisp-Line` or `Execute-Command` (Section 7.8 provides more details.).

Creating Key Bindings

`Display-All-Key-Bindings`

Help⇒This View⇒Keys: Display All

`Bind-Key` *command key-sequence* [*scope*]

Key bindings associate keystroke sequences with commands. The command `Display-All-Key-Bindings` prints the key bindings for the current view into the help view. Key bindings are established or altered using the command `Bind-Key`. The default scope of the change is `:global`; specifying `:view` or `:view-style` within the proper scope makes the change in the local environment. The syntax for `Bind-Key` is

```
(Bind-Key 'function "key sequence" [scope])
```

where *function* is a quoted function name, *key sequence* is a COMMON LISP string specifying a keystroke sequence, and *scope* is either `:view`, `:view-style`, or `:global`. The default value for *scope* is `:global`.

Pan allows you to bind any key sequence to any command. This includes special keys, function keys, mouse buttons, and keys modified by shift or control. Figure 6 shows some of the special keyboard keys (and pseudo-keys, which is how mouse button events are handled in *Pan*) that are known to *Pan* along with their names and default bindings. Most of the names for special keys are derived from and correspond to X11 “keysyms.” Not all of the keys are generated by every keyboard. The default bindings of the “L” function keys are inspired by their labeling on Sun keyboards.

When specifying a keystroke sequence, control characters such as “Control ?” are denoted by the two-character sequence “~?”; the “Escape” prefix is denoted by “Esc”. For example,

```
(Bind-Key 'Delete-Character "~D" :global)
```

establishes the default binding for `Delete-Character`.








Key	Key Name	Binding
" "	Space	Insert-Space-Fill
"~I"	Tab	Self-Insert
"~J"	Newline	Newline-And-Indent
"~M"	Return	Insert-Newline-Fill
"~H"	Backspace	Delete-Previous-Character
"Escape"	Esc	Not bound
"  "	Mouse-Left	Cursor-To-Mouse
"  "	Mouse-Middle	Select-Region-Dot-To-Mouse
"  "	Mouse-Right	Execute-Menu
"  "	Control-Mouse-Left	Oplevel-Cursor-To-Mouse
"Shift-  "	Shift-Mouse-Left	Oplevel-Cursor-To-Mouse
"  "	Control-Mouse-Right	Oplevel-Menu
"Shift-  "	Shift-Mouse-Right	Oplevel-Menu
"_"	Left-Arrow	Oplevel-Cursor-Backward
"_"	Right-Arrow	Oplevel-Cursor-Forward
"↑"	Up-Arrow	Oplevel-Out
"↓"	Down-Arrow	Oplevel-In
"Begin"	Begin	Oplevel-Cursor-To-First
"End"	End	Oplevel-Cursor-To-Last
"Prior"	Prior	Oplevel-Cursor-Backward
"Next"	Next	Oplevel-Cursor-Forward
"Find"	Find	Oplevel-Cursor-Search-Forward
"L1"- "L3"	L1-L3	Not bound
"L4"	L4	Undo
"L5"	L5	Not bound
"L6"	L6	Copy-To-Clipboard
"L7"	L7	Not bound
"L8"	L8	Paste-From-Clipboard
"L9"	L9	Oplevel-Cursor-Search-Forward
"L10"	L10	Cut-To-Clipboard
"F1"- "F10"	F1-F10	Not bound
"R1"- "R15"	R1-R15	Not bound
"Home"	Home	Visit-View-List
"Help"	Help	Visit-Help-View
"Insert"	Insert	Not bound
"Menu"	Menu	Not bound
"Cancel"	Cancel	Not bound
"Break"	Break	Not bound

Figure 6: Bindings and names for special keys

Creating Menu Bindings

Display-Default-Menu	Help⇒This View: Default Menu
Bind-Menu <i>menu-name bindings</i>	
Rebind-Menu <i>menu-name old-label new-item [new-label]</i>	
Create-Menu <i>menu-being-added title bindings</i>	
Copy-Menu <i>old-name new-name [new-title]</i>	

A menu binding associates a menu item with a command or another menu.⁹ The command **Display-Default-Menu** prints the menu bindings for the current view in the help view. Menu bindings are created via the macros **Bind-Menu**, **Copy-Menu**, **Create-Menu**, and **Rebind-Menu**. All menus are global. Any change to a menu affects the global description of that menu. To establish a binding for a menu item in an existing menu, use

```
(Bind-Menu menu-name bindings)
```

where *bindings* is a list of menu items of the form

```
(item ["Selection Name"] [position])
```

The *item* being bound to the menu may be either a command or another menu. The “*Selection Name*” must be a COMMON LISP string. If “*Selection Name*” is omitted, the name of the command or menu is used. The optional argument *position* is an integer - the position in the menu at which to insert the item. The first item in the menu has position 1. For example,

```
(Bind-Menu help-view-style-menu
 (Document-Symbol "Describe" 1))
```

sets up the default binding for **Document-Symbol** as the first item in the **Help** menu and

```
(Bind-Menu text-edit-view-style-menu
 (global-help-menu "Help"))
```

sets up the default binding for the **Help** sub-menu in the **Text** menu.

The macro **Create-Menu** creates a new menu with the given name, title, and bindings. The format for **Create-Menu** is:

```
(Create-Menu menu-name menu-title bindings)
```

For example, the default global **Help** menu is created by the following COMMON LISP code:

⁹A menu item may also be a lisp form.

```
(Create-Menu global-help-menu "Help"
  (this-view-help-menu "This View")
  (help:Apropos-String "Apropos")
  editor-help-menu)
```

Rebind-Menu allows you to change an existing menu item. Its format is:

```
(Rebind-Menu menu-name old-label new [new-label])
```

For example, you could change the menu item *This View: Options* to print the option documentation with the command *Display-Option-Documentation* by the following code:

```
(Rebind-Menu this-view-help-menu
  "Options" Display-Option-Documentation "Option Docs.")
```

Creating Operand Level Bindings

Display-Operand-Level-Bindings	Help⇒This View⇒Operand Cmds.: By Level
Display-Operand-Command-Bindings	Help⇒This View⇒Operand Cmds.: By Command
Display-Operand-Level-Menus	Help⇒This View: Operand Menus
Display-Operand-Level-Documentation	Not bound
Display-Operand-Command-Documentation	Not bound
Oplevel-Menu	^C Mouse-Right
Execute-Oplevel-Menu	Menu at level "Most Operand Levels"
Bind-Oplevel-Command-List	<i>operand-command-command-pair-list level [scope]</i>
Bind-Oplevel-Menu	<i>level menu-name [scope]</i>

Operand level command bindings associate an operand level and a generic command with a *Pan* command. Operand level menu bindings associate an operand level with a menu. The commands *Display-Operand-Level-Bindings*, *Display-Operand-Command-Bindings*, and *Display-Operand-Level-Menus* print into the help view the appropriate bindings in the current view. *Display-Operand-Level-Documentation* and *Display-Operand-Command-Documentation* display documentation about the operand levels and generic "Oplevel-" commands respectively.

Bind-Oplevel-Command-List allows you to create a set of operand level command bindings at a given operand level. Its format is:

```
(Bind-Oplevel-Command-List
  ((operand-command1 command1)
   (operand-command2 command2)
   .
   .
   (operand-commandN commandN))
level [scope])
```

For example, the standard cursor-motion bindings for the operand level “Word” are established by the following code:

```
(Bind-Oplevel-Command-List
  ((Oplevel-Cursor-Forward text:Next-Word)
   (Oplevel-Cursor-Backward text:Previous-Word)
   (Oplevel-Cursor-To-First text:Move-To-First-Word)
   (Oplevel-Cursor-To-Last text:Move-To-Last-Word)
   (Oplevel-Cursor-To-Mouse text:Mouse-Select-Fullword))
word-level)
```

The operand level menu contains, by default, all of the commands which are bound at that level. Operand level menus may be created and altered in exactly the same fashion as other menus. The function `Bind-Oplevel-Menu` binds a menu to an operand level. Its format is:

```
(Bind-Oplevel-Menu level menu-name [scope])
```

For example, this code binds the standard `word-oplevel-menu` to the operand level “Word” in the global scope:

```
(opl:Bind-Oplevel-Menu 'word-level 'word-oplevel-menu)
```

The command `Oplevel-Menu` is a bindable generic command. It is usually bound to the command `Execute-Oplevel-Menu` which executes the menu that is bound to the current operand level. It is possible to rebind `Oplevel-Menu` to a different command for a given operand level; this allows for a highly customizable environment, used at present only for experimental features in `SIMPLE2`.

7.5 Getting and Setting Options

Announce-Option-Variable	Not bound
Set-Global-Option-Variable	Help⇒This View⇒Set Option: Global
Set-View-Style-Option-Variable	Help⇒This View⇒Set Option: View Style
Set-View-Option-Variable	Help⇒This View⇒Set Option: View Only
Set-Buffer-Option-Variable	Not bound
Display-Option-Variables	Help⇒This View: Options

Display-Option-Documentation

Not bound

Much of *Pan*'s behavior may be modified by setting options. The command **Announce-Option-Variable** is used to retrieve the value of an option in the current view. The command prompts for the name of the option and then announces its value in the message line.

The **Set-** commands listed above allow you to set the value of an option in the given scope while running *Pan*. They all prompt for the name of the option and then for its new value, which you must specify in a form acceptable to the COMMON LISP reader.

To set an option's default value to *value*, use the lisp form in your ".panrc" file

```
(setf (variable option-name scope) value)
```

In this case, *scope* must specify either **:view-style** or **:global**. For instance, the expression

```
(setf (variable Window-Close-With-Icon :global) nil)
```

sets the value of the option **Window-Close-With-Icon** to be *nil*. To set any option in a particular view-style, use the macro **With-View-Style-Scope** to specify the view-style (see below). A list of all of the view styles is in Appendix G.

Setting Font Maps

Since the **Text-Window-Fontmap** option is a scoped variable, the macro **With-View-Style-Scope** must be used to set the font for a particular view-style as described in Section 7.2. For example, the help view uses the view-style **help-view-style**; thus a new font map for the help view could be specified by the following code:

```
(With-View-Style-Scope (view-style help-view-style)
  (setf (variable Text-Window-Fontmap :view-style)
    '("-adobe-times-medium-i---12-----*--*"
      "-adobe-new century schoolbook-medium-r---10-----*--*"
      "-adobe-times-bold-r---12-----*--*")))

```

The X tool **XFONTSEL** is useful for determining the exact font you are looking for and getting its full name.

Setting Color Maps

```
Text-Window-Fg-Colormap
Text-Window-Bg-Colormap
Panel-Bg-Color
Panel-Flag-Default-Fg-Color
Panel-Flags-Bg-Color
Panel-Logo-Fg-Color
Panel-Logo-Bg-Color

```


Panel-View-Logo-Fg-Color
 Panel-View-Logo-Bg-Color

Colors are represented in *Pan* as dotted pairs of strings which represent color names, such as ("red"."black"). The first color will be used on a color monitor if the option **Window-Use-Color** is set, otherwise the second color is used. Figure 5 on page 42 shows the uses and default values for the text colormaps in structure-based documents.

Each of the "Panel-" options has the value of a single pair of colors one of which is used for the appropriate area of the panel. You can set a color option by any of the methods you use to set other options. For example, this code would change the **Panel-Flag-Default-Fg-Color** to blue on color screens:

```
(setf (variable Panel-Flag-Default-Fg-Color :global) '("blue"."black"))
```

The **Text-Window-Fg-Colormap** is used for displaying colored or greyed text in textual views. The **Text-Window-Bg-Colormap** is used for displaying colored or greyed background highlight for text in textual views. Each of these two options is an indexed list of color pairs. When a region of text is highlighted or colored in *Pan*, it is assigned an index into the appropriate colormap and displayed with that color.

The X tool **XCOL** will give you a display of the colors that are available on your system.

7.6 Character Sets

Display-Char-Sets	Help⇒This View: Character Sets
Display-Char-Set-Documentation	Not bound
Set-Char-Set <i>char-set-name char-list [scope] [operation]</i>	
Set-Char-Match <i>left-char right-char [scope] [operation]</i>	

These are the normal help commands. **Display-Char-Sets** lists all of the character sets and their contents in the current view. **Display-Char-Set-Documentation** lists the character sets with a description and their default global values.

One particular character set, **match-characters**, contains all of the matched characters such as right and left braces. Whenever *Pan* looks for a balanced expression it tries to find the match for the character under the cursor.

The functions **Set-Char-Set** and **Set-Char-Match** are useful for creating character sets and altering the contents of existing character sets. **Set-Char-Set** allows you to add, delete, or shadow characters in a character set. Its format is:

```
(Set-Char-Set char-set-name char-list [scope] [operation])
```

The *char-list* has the form of a COMMON LISP string of characters. The operation may be one of **:add**, **:delete**, or **:shadow**; it defaults to **:add**. For example, here is the lisp code to add the character "-" to the character set **word-characters**:

```
(Set-Char-Set 'word-characters '"-' )
```

Set-Char-Match allows you to add, delete, or shadow pairs of match characters to the **match-character** set. Its format is:

```
(Set-Char-Match left-char right-char [scope] [operation])
```

For example, here is code to add the characters ">" and "<" to the **match-characters** set:

```
(Set-Char-Match #\< #\> )
```

7.7 Creating and Modifying Flags

Display-Flags

Help⇒This View: Flags

Window-Modify-Flag-Collection

A flag in *Pan* is implemented as an option which can be true or false (in COMMON LISP, **t** or **nil**) and an associated bitmap. The command **Display-Flags** displays all of the flags defined in the current view.

Flags may be added to or removed from any scope with the function **Window-Modify-Flag-Collection**. Its format is:

```
(Window-Modify-Flag-Collection [scope]
  [:add '(add-flag-list)]
  [:delete '(delete-flag-list)]
  [:shadow '(shadow-flag-list)])
```

where *delete-flag-list* is a list of variables in the current collection of flags and *add-flag-list* is a list of flag descriptors of the form:

```
(variable
  [(on-bitmap [ [ on-background-color ] on-foreground-color ])
  [(off-bitmap [ [ off-background-color ] off-foreground-color ])])
```

The bitmap variables both default to **Panel-Flag-Default-Bitmap**, the *on-foreground-color* defaults to **Panel-Flag-Default-Fg-Color**, and the background color variables both default to **Panel-Flags-Bg-Color**. The *off-foreground-color* defaults to **Panel-Flag-Default-Fg-Color** if the *off-bitmap* is set and **Panel-Flags-Bg-Color** if it is not.

All bitmaps and colors used in the descriptor must be defined as variables. For example, to create a new bitmap for the syntax error flag and assign colors and bitmaps for its on and off representations, variables representing all of these pieces of information would have to be defined and set in your **".panrc"** file:

```

(setf (variable Syntax-Errors-Present-Bitmap :global)
      "~/syntax-error.12x12")

(Define-Option-Variable Error-On-Color '("red" . "black")
  "The color to use for the error flags."
  :bindable-scopes :global)
(Define-Variable-Cache Error-On-Color
  'win-sys:color-compute-cache)

(Define-Option-Variable Error-Off-Color '("mediumseagreen" . "black")
  "The color to use for the no error flag."
  :bindable-scopes :global)
(Define-Variable-Cache Error-Off-Color
  'win-sys:color-compute-cache)

(Define-Option-Variable No-Error-Bitmap "~/no-error.12x12"
  "The bitmap which represents the no error flag."
  :bindable-scopes :global)
(Define-Variable-Cache No-Error-Bitmap
  'win-sys:bitmap-compute-cache)

```

See Section 7.8 for more information on defining new options. Then the following code would be included in the appropriate auto-load files:

```

(win:Window-Modify-Flag-Collection :view
  :add
  '((otree:Syntax-Errors-Present?
    (Syntax-Errors-Present-Bitmap Error-On-Color)
    (No-Error-Bitmap Error-Off-Color))))

```

The X tool BITMAP is useful for designing flag bitmaps.

7.8 Lisp-Oriented Commands

Execute-Lisp	Esc Esc
Execute-Command	Esc x
Load-File	^X ^L
Load-From-Selection	Esc ^S
Load-From-Text-Stream	Esc ^X

These commands are mostly for the use of people extending *Pan*, although sometimes you'll want to use one to see what a command does. They are included here for completeness.

Execute-Lisp prompts for a COMMON LISP form to evaluate: the resulting value is printed on the message line. If you want to execute a bindable *Pan* command, there are two methods. The simplest is to invoke **Execute-Command** and respond to the prompt with the name of the command, e.g. **Next-Character**. Alternatively, one can invoke **Execute-Lisp** and respond to the prompt with the expression (**Next-Character**). The parentheses are required in the latter case, since commands are implemented as COMMON LISP functions.

Load-File loads a file of COMMON LISP and *Pan* commands into the system. **Load-From-Text-Stream** loads the contents of the entire text stream in the current view and evaluates the COMMON LISP and *Pan* commands. **Load-From-Selection** loads and evaluates the COMMON LISP and *Pan* commands in the current text selection.

Defining Variables and Options

Define-Option-Variable *option* [*initial-value* [*documentation* [:*apropos*] [:*notifier*]]]
Define-Variable *variable* [*initial-value* [*documentation* [:*apropos*] [:*option*] [:*notifier*]]]

You can create variables and options simply by defining them as COMMON LISP variables in your ".panrc" file. The macro **Define-Variable** allows you to include documentation and apropos information, add notifiers, or make your variable into an option variable known to the help system. The macro **Define-Option-Variable** is the same as **Define-Variable** with :option set to t. As an example, here is COMMON LISP code to create the option variable **Number-Of-Views-Created**:

```
(Define-Option-Variable Number-Of-Views-Created 0
  "the number of views that have been created so far"
  :notifier #'view-num-notifier
  :bindable-scopes :global
  :initial 'nil)
```

Hooks and Notifiers

Display-Hooks	Not bound
Display-Hook-Documentation	Not bound
Display-Notifiers	Not bound
Define-Hook-Function <i>hook scope function</i> [<i>arguments</i>] <i>body</i>	
Define-Hook <i>hook hookable-scopes arguments</i> [<i>documentation</i>] [: <i>apropos</i>]	
Perform-Hook <i>hook arguments</i>	
add-variable-notifier <i>variable notifier</i>	

If you really want to dig into *Pan*'s internals and change things significantly, you may be interested in using hooks and notifiers. This is for ambitious users only!

A **notifier** is a function which is called every time the value of a given variable is changed. Most *Pan* variables and options have notifiers. You can add a notifier to a variable with the function **add-variable-notifier** or you can list the notifier when you declare the variable. Here is COMMON LISP code for a notifier to display the value of the variable in your console window (note that this notifier was listed in the variable definition):

```
(defun view-num-notifier ( foo scope-kind bound new old )
  ( declare ( ignore scope-kind bound old ))
  ( format t "~A is ~A.~%"
    foo new))
```

A **hook** is a place within a function where you can insert new code. The **Define-Hook-Function** macro allows you to add code at an existing hook. Here is an example of a function to increment the option **Number-Of-Views-Created** (defined above) attached to the hook **%view-construction-hook%** which is called immediately after a view is created:

```
(Define-Hook-Function bufview:%view-construction-hook%
  :global
  add-to-view-num
  ()
  ( incf ( variable Number-Of-Views-Created :global)))
```

8 Acknowledgments

Pan is the work of many people. Professor Susan Graham has directed the project since its inception. Robert Ballance was the original architect and continued with the project until completing his Ph.D. Michael Van De Vanter joined the project in its early stages and has been a principal member of the project through the present. Christina Black, Jacob Butcher, Bruce Forstall, Mark Hastings, Darrin Lane, Bill Maddox, Ethan Munson, Tim Wagner, and Robert Wahbe have all made substantial contributions. Finally, we wish to acknowledge the community of “editor people” with whom we have interacted over the past several years. Many of their best ideas appear somewhere within *Pan*.

References

- [1] Robert A. Ballance. *Syntactic and Semantic Checking in Language-Based Editing Systems*. PhD thesis, Computer Science Division, UC Berkeley, December 1989. Available as Technical report number 89/548.
- [2] Robert A. Ballance, Susan L. Graham, and Michael L. Van De Vanter. The *Pan* Language-Based Editing System. *ACM Transactions on Software Engineering and Methodology*, 1991. To Appear.
- [3] Jacob Butcher. *Ladle*. Master's thesis, Computer Science Division, UC Berkeley, November 1989. Available as Technical report number 89/519.
- [4] J. C. Cleaveland and R. C. Uzgalis. *Grammars for Programming Languages*. Elsevier Holland, 1977.
- [5] Bruce Forstall. The *Pan* Engineering Manual. Working Paper 91-1. March 1991.
- [6] Paul N. Hilfinger and Phillip Colella. Fidil: A language for scientific programming. In Robert Grossman, editor, *Symbolic Computation: Applications to Scientific Computing*, pages 97-138. SIAM, 1989.
- [7] R. M. Stallman. EMACS, the Extensible, Customizable, Self-Documenting Display Editor. In *Proc. of the ACM SIGPLAN SIGOA Symposium on Text Manipulation*, pages 147-156, 1981.
- [8] Michael L. Van De Vanter, Robert A. Ballance, and Susan L. Graham. Coherent User Interfaces for Language-Based Editing Systems. *International Journal of Man-Machine Studies*, 1991. To Appear.
- [9] Nicklaus Wirth. *Programming in Modula-2*. Springer-Verlag, third, corrected edition, 1985.

9 Glossary

Active View The view that owns the active window.

Active Window The active window is the window in which the most recent keystroke or mouse action occurred, although the active window may change as the result of a command, for example *Visit-File*.

Apropos A Help command for browsing documentation gathered during definition of *Pan*'s commands, flags, and options. For instance, (*Apropos* "Cursor") lists all of the commands dealing with the cursor.

Auto Load The *Auto-Load* command instructs *Pan* to ensure that a specified file has been loaded whenever a view is created onto a file whose name matches a specified UNIX file expression.

Auto Exec The command *Auto-Exec* instructs *Pan* to execute a specified *function* whenever creating a view having a name that matches a specified pattern.

Backup A copy of the file being visited that records the state of the file before any changes are made using *Pan*. You may visit the backup of a file with the command *Visit-Backup*. You may restore a view of a file to its backed-up state with the command *Revert-Object-To-Backup*.

Binding An association between an event (key-sequence, mouse action, menu selection) and a *Pan* command, used by *Pan*'s command dispatcher to determine the appropriate response to each user event. Every binding is made at a *scope*: global, for a specified view style, or for a specific view instance.

Character Set A named set of ASCII characters, scoped as with all other *Pan* bindings. Character sets are used to define simple structural attributes of ordinary text: words, white-space, matching brackets, and the like.

Checkpoint A copy of a file being visited that records an intermediate, modified state of the file. *Pan* makes a checkpoint periodically as the text in a view is modified; each checkpoint replaces the previous one. You may visit separately the most recent checkpoint of a file with the command *Visit-Checkpoint*. You may restore a view of a file to its most recently checkpointed state with the command *Revert-Object-To-Checkpoint*.

Clipboard A ring, shared by all views, that contains one or more regions of text. The clipboard supports copy, cut, and paste among views, or between *Pan* and other processes.

Command An operation that may be invoked directly by users through bindings to keystroke sequences and menus. *Pan* commands are defined using *Define-Command*. They are implemented as and may also be called as COMMON LISP functions.

Current Operand Level See *Operand Level*.

Cut Remove a region of text from the active text stream and push it onto the clipboard.

Cycle Make the current top item in a ring become the oldest item, moving all other values up—the second youngest becoming the new top item.

Default Font The first element in the font list specified by option *Text-Window-Fontmap*. When any other slot in a map is unspecified, the default font is used.

Delete Remove a region of text from the active text stream, keeping no copies other than possibly in undo history.

Deselect Ensure that there is no selection in the active view, without affecting the view's contents.

Directory Editor A *Pan* view style for browsing and operating upon UNIX file system directories.

Dot An anachronistic internal name for *Pan*'s text cursor. The function *Dot* returns the integer offset (in characters, zero-based) of the text cursor from the beginning of the file.

Edit Object Whatever can be displayed and possibly manipulated by a *Pan* view, closely related to the *Emacs* notion of "buffer." A *Pan* session instantiates an edit object for each text file, program or directory being viewed; each edit object comprises a copy of the data being edited, one or more views, and other information.

Edit Window That area of a *Pan* window in which part of the object being edited is displayed to the user.

Expression A balanced bracket expression is a string of characters enclosed within matched left and right braces, brackets, parentheses, or other matched characters, and which may contain nested pairs of balanced match characters. Character set declarations specify which characters are to be treated as matching characters.

Fill Rearrange lines of text so that all are of approximately the same length, as controlled by option *Text-Line-Length*.

Flag A *Pan* variable that has been configured specially in some scope so that its (boolean) value appears on the information panel of all windows in that scope. At the flag's panel location will appear one specified graphical appearance when the variable's (scoped) value is on (non-*nil*) and another specified graphical appearance when the variable's value is off (*nil*).

Font Map A zero-indexed list of font names, containing from 1 to 8 names, that specifies how font codes stored in *Pan*'s internal text representation are to be interpreted during display operations.

Frame The outer surrounding edge of a window that responds to X window protocols.

Generic Operation A *Pan* command, such as **Cursor-Forward** or **Delete**, whose behavior is determined dynamically by dispatch on the current operand level of the active window and by operand bindings.

Global Image A small inset within a *Pan* graphical window that summarizes the entire graph being viewed, regardless of zoom and scroll state. It also marks specially that portion of the entire graph that is visible in the rest of the window. The global image can be resized by the user and can be toggled on or off.

Graphical View A *Pan* view that displays information in terms of boxes (possibly containing text) and lines that connect them.

Help View A special *Pan* view used for displaying help information.

Hook A place within *Pan*'s thread of control where new code can be inserted conveniently. The **Define-Hook** creates a hook, **Define-Hook-Function** adds code to the hook, and **Perform-Hook** executes the hook's code.

Implicit Selection The text region between the text cursor and the top mark of the mark stack. This is distinct from and secondary to the visible selection in each view.

Information Panel The upper portion of every *Pan* window, which contains information about the current view, such as the language, the operand level, and displayed flags.

Internal Tree *Pan*'s internal representation for programs and other language-structured objects. It is generated by the syntactic analyzer (parser) from the lexical stream. The details are generally hidden from users and are revealed only through the operand level mechanisms.

Key Binding An association between a sequence of keyboard (or mouse button) events and a *Pan* command, used by *Pan*'s command dispatcher to determine the appropriate response to each user event. In some cases (prefix keys) the response may be to wait for another keyboard event. Every key binding is made at a *scope*: global, for a specified *view style*, or for a specific *view instance*.

Kill Remove a region of text from the active text stream and push it onto the active view's kill ring (or to the clipboard, depending on option **Kills-To-Clipboard**).

Kill Ring A ring, local to each view, that contains one or more regions of text. The kill ring supports copy, cut, and paste within a single textual view.

Load Read into *Pan*'s execution image a collection of COMMON LISP and *Pan* commands, executing top level forms.

Lexeme The smallest unit known to the syntactic analyzer. Lexemes include variable names, arithmetic and assignment operators, and keywords.

Lexical Analysis The process of reading a text stream and constructing an appropriate stream of lexemes, according to an underlying language description. Lexical analysis in *Pan* is incremental, only making changes to the lexical stream where needed because of changes to the text stream since the previous analysis.

Mark A character position in a text stream that is guaranteed to remain in the stream, even when an underlying character is deleted (in which case the mark is moved rightward). A mark is attached to a character, not an offset, so deletions before a mark do not affect the character to which a mark refers.

Mark Stack Each *Pan* text stream provides for a stack of marks, the top element of which is known as simply "the mark". These values may be popped and pushed as in any stack.

Menu Binding An association between a menu or submenu title and a *Pan* command, used by *Pan*'s command dispatcher to determine the appropriate response to each menu operation by the user. Every key binding is made at a *scope*: global, for a specified *view style*, or for a specific view instance.

Message Line The lowermost part of the information panel in each *Pan* window, used to display a single line of text containing various information: incomplete key sequences, information about time consuming operations being performed, and the output of some commands.

Minor Mode A collection of bindings that may be added to particular view instances, providing a slight variation on one of *Pan*'s established view styles.

Mouse Icon A graphical token that shows the location of the mouse on the workstation screen. The mouse icon is normally an arrow when the mouse is positioned within a *Pan* window, as specified by option **Window-Default-Mouse-Icon**. Different mouse icons appear when *Pan* is busy working (not responding to user events) or to suggest a different function for the mouse in a region.

Node A structural component of *Pan*'s internal tree representation, used to represent a meaningful part of a program or other structured document.

Notifier A function that may be associated with a *Pan* variable, using either the *Lisp*:*notifier* keyword with **Define-Variable** and **Define-Option-Variable** or the function *Lisp*:*add-variable-notifier*. Whenever the value of a *Pan* variable in a particular scope changes, all associated notifiers are called with information about the old and new values.

Numeric Prefix An optional (default 1) integer argument to each *Pan* command invocation, supplied by special sequences of prefix keyboard events. Not all commands use the numeric prefix, and some check only for its existence and not its value.

Operand Level An element of *Pan* window state, always visible in the panel, which modulates the behavior of certain generic (or *level-sensitive*) operations like **Cursor-Forward** or **Delete**. The current level is selected by the user, from among those specified by option **Operand-Level-Choices**, using either the panel menu or by invoking level-specific commands such as **Set-Oplevel-To-Character**, and **Set-Oplevel-To-Declaration**.

Operand Level Binding A three-way association of an operand level (for example *Character at level “)”*), a generic (or *level-sensitive*) operation (for example **Cursor-Forward**), and a *Pan* command (for example **Next-Character**). These bindings are used by *Pan*'s command dispatcher to determine the appropriate response to each user invocation of a generic command. Every binding is made at a *scope*: *global*, for a specified *view style*, or for a specific view instance.

Operand Level Menu A menu associated with a particular operand level; the command **Oplevel-Menu** by default presents the user with the menu appropriate to the current level. These menus normally display all of the operand level bindings for the generic commands at the given level.

Option A user-definable, user-modifiable, typed *Pan* variable. Every value is assigned at a *scope*: *global*, for a specified *view style*, or for a specific view instance. Many of the customizations available to a user are provide via predefined options. Option values may be made visible in *Pan*'s windows; see *flags*. Options may be made “active values” by the addition of *notifiers*.

Parsing See *syntactic analysis*.

Paste Copy a region of text from the top of the clipboard into the current text stream.

Pop-Up Window A small window which appears on the screen to accept a textual argument to a command or to obtain a response to a question.

Prefix Keys Keyboard events that are not bound to a command but which form prefixes to sequences which are bound. Any key may be a prefix in *Pan*; the keys “**Escape**”, “**^X**”, “**^C**”, and “**^Z**” are used as prefix keys for in *Pan*'s default key bindings.

Protected The contents of a file, directory, or other editable object which is protected may not be altered.

Region A contiguous sequence of characters in a *Pan* text stream. Most text operations involve regions either as source, destination, or both.

Replace 1. A “Replace-” command searches for instances of a given pattern and replaces them with a given string. 2. A region of text may be replaced by another region of text from the kill ring or clipboard.

Ring A circular bounded stack. Adding an item to a ring pushes the other items just like a bounded stack. The oldest value in the stack may be discarded to preserve the boundedness. Rings can also be cycled.

Scope The scope of an option or binding determines the set of *Pan* views in which the option or binding is effective. Normal configurations occur in one of three scopes: global, for a specified view style, or for a specific view instance.

Scroll Bars The scroll bars are found on the borders of a *Pan* window and allow you to scroll the window with the mouse.

Scrolling Scrolling a window moves the region of the view which is currently visible in the window vertically or horizontally.

Search *Pan* provides commands which search for strings that match specified regular expressions.

Selection A specially designated region in textual views, distinguished by underlining in all text windows. There is at most one selection per view.

Semantic Analysis The process of analyzing a program and its associated database of derived information, according to the *Colander* portion of an underlying language description. Results of semantic analysis include facts asserted in the database and diagnosis of program components at which *Colander* constraints (typically including, but not limited to, the static semantics of the language) are not satisfied. Semantic analysis in *Pan* is incremental, only making changes to the database where needed because of changes to the internal tree since the previous analysis. The **Database-Updated?** is on in a view if and only if semantic analysis has been performed since the most recent textual or database change.

Shadow When you shadow a binding in a given scope, it effectively removes any binding inherited from an enclosing scope if any such binding exists.

Structural Cursor A reference to some component in the internal tree representation of a structured object, shared by all views on that object.

Syntactic Analysis The process of reading a lexical stream and constructing an appropriate internal tree, according to an underlying language description (also known as parsing). Syntactic analysis in *Pan* is incremental, only making changes to the internal tree where needed because of changes to the lexical stream since the previous analysis. The flag **Parse-Is-Current?** is on in a view if and only if lexical and syntactic analysis have been performed since the most recent textual change.

Text Cursor The location where alterations to a text stream can occur, displayed as an inverted box in all text windows. Characters are inserted or deleted at the character position to the left of the character designated by the cursor.

Undo Return the state of an edit object to a state it was in before a recent modification.

Unsatisfied Constraints Contextual constraints from the *Colander* description of the underlying language which are not met in the program.

View A view is a format for viewing an object. Any object may have several views. For example, a program may have a text view, a tree view, a subtree view, and a database view. A view may have more than one window. Each view has associated state information which is shared by all windows on that view.

View List A *Pan* view style for browsing and operating on the list of all view instances in a *Pan* session. Quitting the view list terminates *Pan*.

View-Style A configurable editing context. *Pan* has several different view-styles and every view must belong to some view-style.

Window The equivalent of a window in *Emacs*, a window displays a view. Each text window has its own text cursor but all other state is shared by other windows on the same view.

Yank Copy a region of text from the top of the kill ring into the current text stream.

A Default Key Bindings

A.1 Bindings by Command Name in a Text View

Announce-Text-Cursor-Info	<code>^X =</code>	Forward-Vscroll-Current-Window	<code>^V</code>
Backward-Expr	<code>Esc ^B</code>	Goto-Line	<code>^X L</code>
Backward-Vscroll-Current-Window	<code>Esc V</code>	Goto-Line	<code>^X l</code>
Backward-Vscroll-Current-Window	<code>Esc v</code>	Indent-Like-Previous-Line	<code>Esc Tab</code>
Capitalize-Selection	<code>Esc ^C</code>	Insert-File	<code>^X ^I</code>
Capitalize-Word	<code>Esc C</code>	Insert-Newline-Fill	<code>Return</code>
Capitalize-Word	<code>Esc c</code>	Insert-Parentheses	<code>Esc (</code>
Close-Current-Window	<code>^X O</code>	Insert-Space-Fill	<code>Space</code>
Copy-Selection-As-Kill	<code>Esc W</code>	Interrupt-Editor	<code>^X ^Z</code>
Copy-Selection-As-Kill	<code>Esc w</code>	Just-One-Space	<code>Esc Space</code>
Copy-Selection-To-Cursor	<code>Esc ^Y</code>	Kill-Expr	<code>Esc ^K</code>
Copy-To-Clipboard	<code>L6</code>	Kill-Previous-Word	<code>Esc Delete</code>
Cursor-To-Mouse	<code>Mouse-Left</code>	Kill-Selected-Region	<code>^W</code>
Cut-To-Clipboard	<code>L10</code>	Kill-To-Eol	<code>^K</code>
Cycle-Paste	<code>Esc L8</code>	Kill-Word	<code>Esc D</code>
Cycle-Show-Clipboard	<code>Esc !</code>	Kill-Word	<code>Esc d</code>
Cycle-Show-Kill	<code>^X !</code>	Left-Hscroll-Current-Window	<code>^X <</code>
Cycle-Yank	<code>Esc Y</code>	Load-File	<code>^X ^L</code>
Cycle-Yank	<code>Esc y</code>	Load-From-Selection	<code>Esc ^S</code>
Delete-Blank-Lines	<code>^X ^O</code>	Load-From-Text-Stream	<code>Esc ^X</code>
Delete-Character	<code>^D</code>	Lowercase-Selection	<code>Esc ^L</code>
Delete-Horizontal-Space	<code>Esc \</code>	Lowercase-Word	<code>Esc L</code>
Delete-Indentation	<code>Esc ^</code>	Lowercase-Word	<code>Esc l</code>
Delete-Previous-Character	<code>Backspace</code>	Mouse-Extend-Selection-Fullword	<code>Esc Mouse-Middle</code>
Delete-Previous-Character	<code>Delete</code>	Mouse-Select-Fullword	<code>Esc Mouse-Left</code>
Deselect-Region	<code>Esc ^D</code>	Move-Selection-To-Cursor	<code>Esc Return</code>
Display-Objects	<code>^X ^B</code>	Move-To-Bol	<code>^A</code>
Editor-Error	<code>Esc ^G</code>	Move-To-Bos	<code>Esc <</code>
Editor-Error	<code>^C ^G</code>	Move-To-Eol	<code>^E</code>
Editor-Error	<code>^C Cancel</code>	Move-To-Eos	<code>Esc ></code>
Editor-Error	<code>^G</code>	Newline-And-Indent	<code>Newline</code>
Editor-Error	<code>^X ^G</code>	Next-Character	<code>^F</code>
Editor-Error	<code>^X Cancel</code>	Next-Line	<code>^N</code>
Editor-Error	<code>^Z ^G</code>	Next-Message-Current-Window	<code>Esc N</code>
Editor-Error	<code>^Z Cancel</code>	Next-Message-Current-Window	<code>Esc n</code>
Editor-Error	<code>Cancel</code>	Next-Word	<code>Esc F</code>
Editor-Error	<code>Esc Cancel</code>	Next-Word	<code>Esc f</code>
Execute-Command	<code>Esc X</code>	Open-Another-Window-In-View	<code>^X 2</code>
Execute-Command	<code>Esc x</code>	Open-Line	<code>^O</code>
Execute-Lisp	<code>Esc Esc</code>	Oplevel-Cursor-Backward	<code>Left-Arrow</code>
Execute-Menu	<code>Mouse-Right</code>	Oplevel-Cursor-Backward	<code>^C ^B</code>
Exit-Editor	<code>^X ^C</code>	Oplevel-Cursor-Backward	<code>Prior</code>
First-Non-Blank	<code>Esc M</code>	Oplevel-Cursor-Forward	<code>Right-Arrow</code>
First-Non-Blank	<code>Esc m</code>	Oplevel-Cursor-Forward	<code>^C ^F</code>
Forward-Expr	<code>Esc ^F</code>	Oplevel-Cursor-Forward	<code>Next</code>
		Oplevel-Cursor-In	<code>^C ^I</code>
		Oplevel-Cursor-In	<code>Down-Arrow</code>
		Oplevel-Cursor-Out	<code>^C ^D</code>
		Oplevel-Cursor-Out	<code>Up-Arrow</code>
		Oplevel-Cursor-Search-Backward	<code>^C ^R</code>
		Oplevel-Cursor-Search-Forward	<code>^C ^S</code>
		Oplevel-Cursor-Search-Forward	<code>Find</code>

Oplevel-Cursor-Search-Forward	L9	Self-Insert	!to~
Oplevel-Cursor-To-First	^C Esc <	Self-Insert	Tab
Oplevel-Cursor-To-First	^C <	Set-Mark	^Q
Oplevel-Cursor-To-First	Begin	Set-Oplevel-To-Character	^C c
Oplevel-Cursor-To-Last	^C Esc >	Set-Oplevel-To-Line	^C l
Oplevel-Cursor-To-Last	^C >	Set-Oplevel-To-Word	^C w
Oplevel-Cursor-To-Last	End	Set-Text-Fill-Prefix	^X .
Oplevel-Cursor-To-Mouse	Control-Mouse-Left	Set-Text-Line-Length	^X F
Oplevel-Cursor-To-Mouse	Shift-Mouse-Left	Set-Text-Line-Length	^X f
Oplevel-Cursor-To-Mouse	^C Mouse-Left	Show-Clipboard	Esc ?
Oplevel-Delete	^C ^D	Show-Kill	^X ?
Oplevel-Menu	Control-Mouse-Right	Show-Match	Esc %
Oplevel-Menu	Shift-Mouse-Right	Split-Line	Esc ^O
Oplevel-Menu	^C Mouse-Right	Swap-Dot-And-Mark	^X ^X
Oplevel-Mouse-Extend	Control-Mouse-Middle	Text-Fill-To-Blank-Line	Esc Q
Oplevel-Mouse-Extend	Shift-Mouse-Middle	Text-Fill-To-Blank-Line	Esc q
Oplevel-Mouse-Extend	^C Mouse-Middle	Toggle-Object-Protection	^X ^Q
Oplevel-Query-Replace-All	^C Esc ^R	Toggle-Text-Fill	^X ^A
Oplevel-Replace-All	^C Esc R	Transpose-Characters	^T
Oplevel-Replace-All	^C Esc r	Transpose-Lines	^X ^T
Oplevel-Select	^C Backspace	Undo	L4
Paste-From-Clipboard	L8	Undo	^X U
Prefix	^U	Undo	^X u
Preserve-All-Objects	^X Return	Uppercase-Selection	Esc ^U
Prev-Message-Current-Window	Esc P	Uppercase-Word	Esc U
Prev-Message-Current-Window	Esc p	Uppercase-Word	Esc u
Previous-Character	^B	Visit-Directory	^X D
Previous-Line	^P	Visit-Directory	^X ^D
Previous-Word	Esc B	Visit-Directory	^X d
Previous-Word	Esc b	Visit-File	^X ^F
Protected-Visit-File	^X ^R	Visit-Help-View	Help
Query-Replace-All	Esc ^R	Visit-Symbol-Definition	Esc .
Quote-Character	^Q	Visit-View	^X B
Re-Search-Backward	^R	Visit-View	^X b
Re-Search-Forward	^S	Visit-View-List	Home
Redo	^X R	Visit-View-List	R7
Redo	^X r	Yank-From-Kill-Ring	^Y
Redraw-Current-Window	^L		
Remove-View	^X K		
Remove-View	^X k		
Replace-All	Esc R		
Replace-All	Esc r		
Revert-Object	^X Backspace		
Right-Hscroll-Current-Window	^X >		
Save-Object-Copy-As	^X ^W		
Save-Object	^X ^S		
Select-Expr	Esc ^Q		
Select-Region-Dot-To-Mark	Esc ^W		
Select-Region-Dot-To-Mouse	Mouse-Middle		
Select-Text-Stream	^X H		
Select-Text-Stream	^X h		
Select-Word	Esc @		

A.2 Bindings by Key in a Text View

~Q	Set-Mark	~X ~G	Editor-Error
~A	Move-To-Bol	~X Backspace	Revert-Object
~B	Previous-Character	~X ~I	Insert-File
~C ~B	Oplevel-Cursor-Backward	~X ~L	Load-File
~C ~D	Oplevel-Delete	~X Return	Preserve-All-Objects
~C ~F	Oplevel-Cursor-Forward	~X ~O	Delete-Blank-Lines
~C ~G	Editor-Error	~X ~Q	Toggle-Object-Protection
~C Backspace	Oplevel-Select	~X ~R	Protected-Visit-File
~C ~I	Oplevel-Cursor-In	~X ~S	Save-Object
~C ~O	Oplevel-Cursor-Out	~X ~T	Transpose-Lines
~C ~R	Oplevel-Cursor-Search-Backward	~X ~W	Save-Object-Copy-As
~C ~S	Oplevel-Cursor-Search-Forward	~X ~X	Swap-Dot-And-Mark
~C Esc ~R	Oplevel-Query-Replace-All	~X ~Z	Interrupt-Editor
~C Esc <	Oplevel-Cursor-To-First	~X !	Cycle-Show-Kill
~C Esc >	Oplevel-Cursor-To-Last	~X .	Set-Text-Fill-Prefix
~C Esc R	Oplevel-Replace-All	~X 0	Close-Current-Window
~C Esc r	Oplevel-Replace-All	~X 2	Open-Another-Window-In-View
~C <	Oplevel-Cursor-To-First	~X <	Left-Hscroll-Current-Window
~C >	Oplevel-Cursor-To-Last	~X =	Announce-Text-Cursor-Info
~C c	Set-Oplevel-To-Character	~X >	Right-Hscroll-Current-Window
~C l	Set-Oplevel-To-Line	~X ?	Show-Kill
~C w	Set-Oplevel-To-Word	~X B	Visit-View
~C Mouse-Left	Oplevel-Cursor-To-Mouse	~X D	Visit-Directory
~C Mouse-Middle	Oplevel-Mouse-Extend	~X F	Set-Text-Line-Length
~C Mouse-Right	Oplevel-Menu	~X H	Select-Text-Stream
~C Cancel	Editor-Error	~X K	Remove-View
~D	Delete-Character	~X L	Goto-Line
~E	Move-To-Eol	~X R	Redo
~F	Next-Character	~X U	Undo
~G	Editor-Error	~X b	Visit-View
Backspace	Delete-Previous-Character	~X d	Visit-Directory
Tab	Self-Insert	~X f	Set-Text-Line-Length
Newline	Newline-And-Indent	~X h	Select-Text-Stream
~K	Kill-To-Eol	~X k	Remove-View
~L	Redraw-Current-Window	~X l	Goto-Line
Return	Insert-Newline-Fill	~X r	Redo
~N	Next-Line	~X u	Undo
~O	Open-Line	~X Cancel	Editor-Error
~P	Previous-Line	~Y	Yank-From-Kill-Ring
~Q	Quote-Character	~Z ~G	Editor-Error
~R	Re-Search-Backward	~Z Cancel	Editor-Error
~S	Re-Search-Forward	Esc ~Q	Select-Expr
~T	Transpose-Characters	Esc ~B	Backward-Expr
~U	Prefix	Esc ~C	Capitalize-Selection
~V	Forward-Vscroll-Current-Window	Esc ~D	Deselect-Region
~W	Kill-Selected-Region	Esc ~F	Forward-Expr
~X ~A	Toggle-Text-Fill	Esc ~G	Editor-Error
~X ~B	Display-Objects	Esc Tab	Indent-Like-Previous-Line
~X ~C	Exit-Editor	Esc ~K	Kill-Expr
~X ~D	Visit-Directory	Esc ~L	Lowercase-Selection
~X ~F	Visit-File	Esc Return	Move-Selection-To-Cursor
		Esc ~O	Split-Line

Esc ~R	Query-Replace-All	Esc L8	Cycle-Paste
Esc ~S	Load-From-Selection	Space	Insert-Space-Fill
Esc ~U	Uppercase-Selection	!to~	Self-Insert
Esc ~W	Select-Region-Dot-To-Mark	Delete	Delete-Previous-Character
Esc ~X	Load-From-Text-Stream	Mouse-Left	Cursor-To-Mouse
Esc ~Y	Copy-Selection-To-Cursor	Mouse-Middle	Select-Region-Dot-To-Mouse
Esc Esc	Execute-Lisp	Mouse-Right	Execute-Menu
Esc Space	Just-One-Space	Control-Mouse-Left	Oplevel-Cursor-To-Mouse
Esc !	Cycle-Show-Clipboard	Control-Mouse-Middle	Oplevel-Mouse-Extend
Esc %	Show-Match	Control-Mouse-Right	Oplevel-Menu
Esc (Insert-Parentheses	Shift-Mouse-Left	Oplevel-Cursor-To-Mouse
Esc .	Visit-Symbol-Definition	Shift-Mouse-Middle	Oplevel-Mouse-Extend
Esc <	Move-To-Bos	Shift-Mouse-Right	Oplevel-Menu
Esc >	Move-To-Eos	Home	Visit-View-List
Esc ?	Show-Clipboard	Left-Arrow	Oplevel-Cursor-Backward
Esc @	Select-Word	Up-Arrow	Oplevel-Cursor-Out
Esc B	Previous-Word	Right-Arrow	Oplevel-Cursor-Forward
Esc C	Capitalize-Word	Down-Arrow	Oplevel-Cursor-In
Esc D	Kill-Word	Prior	Oplevel-Cursor-Backward
Esc F	Next-Word	Next	Oplevel-Cursor-Forward
Esc L	Lowercase-Word	End	Oplevel-Cursor-To-Last
Esc M	First-Non-Blank	Begin	Oplevel-Cursor-To-First
Esc N	Next-Message-Current-Window	Find	Oplevel-Cursor-Search-Forward
Esc P	Prev-Message-Current-Window	Cancel	Editor-Error
Esc Q	Text-Fill-To-Blank-Line	Help	Visit-Help-View
Esc R	Replace-All	L4	Undo
Esc U	Uppercase-Word	L6	Copy-To-Clipboard
Esc V	Backward-Vscroll-Current-Window	L8	Paste-From-Clipboard
Esc W	Copy-Selection-As-Kill	L9	Oplevel-Cursor-Search-Forward
Esc X	Execute-Command	L10	Cut-To-Clipboard
Esc Y	Cycle-Yank	R7	Visit-View-List
Esc \	Delete-Horizontal-Space		
Esc ^	Delete-Indentation		
Esc b	Previous-Word		
Esc c	Capitalize-Word		
Esc d	Kill-Word		
Esc f	Next-Word		
Esc l	Lowercase-Word		
Esc m	First-Non-Blank		
Esc n	Next-Message-Current-Window		
Esc p	Prev-Message-Current-Window		
Esc q	Text-Fill-To-Blank-Line		
Esc r	Replace-All		
Esc u	Uppercase-Word		
Esc v	Backward-Vscroll-Current-Window		
Esc w	Copy-Selection-As-Kill		
Esc x	Execute-Command		
Esc y	Cycle-Yank		
Esc Delete	Kill-Previous-Word		
Esc Mouse-Left	Mouse-Select-Fullword		
Esc Mouse-Middle	Mouse-Extend-Selection-Fullword		
Esc Cancel	Editor-Error		

A.3 Special Key Bindings in the View List

~B	Previous-Line-Select
~F	Next-Line-Select
~N	Next-Line-Select
~P	Previous-Line-Select
f	Visit-Selected-View
x	Remove-Selected-View
Mouse-Left	Mouse-Select-Full-Line
Mouse-Middle	Mouse-Select-Full-Line
Left-Arrow	Previous-Line-Select
Up-Arrow	Previous-Line-Select
Right-Arrow	Next-Line-Select
Down-Arrow	Next-Line-Select

A.4 Special Key Bindings in the Help View

Mouse-Left	Mouse-Select-Fullword
Mouse-Middle	Mouse-Extend-Selection-Fullword
Left-Arrow	Previous-Character
Right-Arrow	Next-Character

A.5 Special Key Bindings in a Directory Editor

~B	Previous-Line-Select
~D	Dired-Mark-Selection
~F	Next-Line-Select
~N	Next-Line-Select
~P	Previous-Line-Select
~R	Dired-Visit-Read-Only
Escape Mouse-Left	Mouse-Select-Full-Line
Escape Mouse-Middle	Mouse-Extend-Selection-Full-Line
#	Dired-Mark-Editor-Files
D	Dired-Mark-Selection
F	Dired-Visit
G	Revert-Object
Q	Remove-Object
U	Dired-Unmark-Selection
X	Dired-Delete-Files
d	Dired-Mark-Selection
f	Dired-Visit
g	Revert-Object
q	Remove-Object
u	Dired-Unmark-Selection
x	Dired-Delete-Files
Mouse-Left	Mouse-Select-Full-Line
Mouse-Middle	Mouse-Extend-Selection-Full-Line

Left-Arrow	Previous-Line-Select
Up-Arrow	Previous-Line-Select
Right-Arrow	Next-Line-Select
Down-Arrow	Next-Line-Select
L10	Dired-Mark-Selection

A.6 Special Key Bindings in a Language-Based View (SIMPLE2)

~C ~X =	Announce-Structure-Cursor-Info
~C !	Set-Oplevel-To-Syntactic-Error
~C #	Set-Oplevel-To-Semantic-Error
~C =	Announce-Structure-Cursor-Node-Name
~C @	Set-Oplevel-To-Simple2-Placeholder
~C a	Analyze-Changes
~C d	Set-Oplevel-To-Simple2-Declaration
~C e	Set-Oplevel-To-Simple2-Expression
~C p	Set-Oplevel-To-Simple2-Placeholder
~C q	Set-Oplevel-To-Query
~C s	Set-Oplevel-To-Simple2-Statement
~C x	Set-Oplevel-To-Lexeme
Escape ~D	Clear-Structure-Cursor

A.7 Special Key Bindings in a Graphical View

a	Zoom-Reset
e	Global-Image-Enlarge
g	Global-Image-Toggle
i	Zoom-In
o	Zoom-Out
s	Global-Image-Shrink

B Default Menu Bindings

B.1 Bindings in an Ordinary Text View by Command Name

Append-Selection-To-File	Text Edit⇒File: Append Selection To...
Apropos-String	Help: Apropos
Close-Current-Window	Window: Close
Copy-Selection-To-Cursor	Text Edit: Copy To Cursor
Copy-To-Clipboard	Clipboard: Copy
Cut-To-Clipboard	Clipboard: Cut
Cycle-Show-Clipboard	Clipboard: Cycle and Show
Display-All-Key-Bindings	Help⇒This View⇒Keys: Display All
Display-Auto-Exec	Help⇒Pan: Filename Auto-Exec Map
Display-Auto-Load	Help⇒Pan: Filename Auto-Load Map
Display-Bug-Report-Info	Help⇒Pan: How To Report Bugs
Display-Char-Sets	Help⇒This View: Char. Sets
Display-Commands	Help⇒Pan: Commands Available
Display-Default-Menu	Help⇒This View: Default Menu
Display-Flags	Help⇒This View: Flags
Display-Key-Bindings-For-Command	Help⇒This View⇒Keys: Command - Key>
Display-Key-Binding	Help⇒This View⇒Keys: Key - Command>
Display-Language-List	Help⇒Pan: Language Descriptions Loaded
Display-Objects	Help⇒Pan: Objects Being Viewed
Display-Operand-Command-Bindings	Help⇒This View⇒Operand Cmds.: By Command
Display-Operand-Level-Bindings	Help⇒This View⇒Operand Cmds.: By Level
Display-Operand-Level-Menus	Help⇒This View: Operand Menus
Display-Option-Variables	Help⇒This View: Options
Display-Version	Help⇒Pan: Version
Insert-File	Text Edit⇒File: Insert Text From...
Kill-Selected-Region	Text Edit: Kill
Move-Selection-To-Cursor	Text Edit: Move To Cursor
Open-Another-Window-In-View	Window: Open Another
Paste-From-Clipboard	Clipboard: Paste
Redo	Undo: Redo
Redraw-Current-Window	Window: Redraw
Remove-View	View: Remove
Revert-Object	Store: Revert
Save-Object-Copy-As	Store: Save Copy As...
Save-Object	Store: Save
Scroll-To-Cursor-Current-Window	Window: Scroll to Cursor
Set-Global-Option-Variable	Help⇒This View⇒Set Option: Global
Set-View-Option-Variable	Help⇒This View⇒Set Option: View Only
Set-View-Style-Option-Variable	Help⇒This View⇒Set Option: View Style
Show-Clipboard	Clipboard: Show Contents
Sub-Redo	Undo: Sub-Redo
Sub-Undo	Undo: Sub-Undo
Toggle-Object-Protection	Text Edit: Toggle Protection
Undo	Undo: Undo
Visit-File	Store: Visit New...
Write-Selection-To-File	Text Edit⇒File: Write Selection To...
Yank-From-Kill-Ring	Text Edit: Yank

B.2 Bindings in an Ordinary Text View by Menu

Clipboard: Cut	Cut-To-Clipboard
Clipboard: Copy	Copy-To-Clipboard
Clipboard: Paste	Paste-From-Clipboard
Clipboard: Show Contents	Show-Clipboard
Clipboard: Cycle and Show	Cycle-Show-Clipboard
Text Edit: Kill	Kill-Selected-Region
Text Edit: Yank	Yank-From-Kill-Ring
Text Edit: Copy To Cursor	Copy-Selection-To-Cursor
Text Edit: Move To Cursor	Move-Selection-To-Cursor
Text Edit: File	Insert-File
Insert Text From... Text Edit⇒File: Write Selection To...	Write-Selection-To-File
Text Edit⇒File: Append Selection To...	Append-Selection-To-File
Text Edit: Toggle Protection	Toggle-Object-Protection
Undo: Undo	Undo
Undo: Redo	Redo
Undo: Sub-Undo	Sub-Undo
Undo: Sub-Redo	Sub-Redo
Store: Save	Save-Object
Store: Save Copy As...	Save-Object-Copy-As
Store: Revert	Revert-Object
Store: Visit New...	Visit-File
View: Remove	Remove-View
Window: Close	Close-Current-Window
Window: Open Another	Open-Another-Window-In-View
Window: Scroll to Cursor	Scroll-To-Cursor-Current-Window
Window: Redraw	Redraw-Current-Window
Help⇒This View⇒Keys: Display All	Display-All-Key-Bindings
Help⇒This View⇒Keys: Key - Command>	Display-Key-Binding
Help⇒This View⇒Keys: Command - Key>	Display-Key-Bindings-For-Command
Help⇒This View: Default Menu	Display-Default-Menu
Help⇒This View⇒Operand Cmds.: By Level	Display-Operand-Level-Bindings
Help⇒This View⇒Operand Cmds.: By Command	Display-Operand-Command-Bindings
Help⇒This View: Operand Menus	Display-Operand-Level-Menus
Help⇒This View: Options	Display-Option-Variables
Help⇒This View⇒Set Option: View Only	Set-View-Option-Variable
Help⇒This View⇒Set Option: View Style	Set-View-Style-Option-Variable
Help⇒This View⇒Set Option: Global	Set-Global-Option-Variable
Help⇒This View: Flags	Display-Flags
Help⇒This View: Char. Sets	Display-Char-Sets
Help: Apropos	Apropos-String
Help⇒Pan: Objects Being Viewed	Display-Objects
Help⇒Pan: Language Descriptions Loaded	Display-Language-List
Help⇒Pan: Commands Available	Display-Commands
Help⇒Pan: Filename Auto-Load Map	Display-Auto-Load
Help⇒Pan: Filename Auto-Exec Map	Display-Auto-Exec
Help⇒Pan: Version	Display-Version
Help⇒Pan: How To Report Bugs	Display-Bug-Report-Info

B.3 Additional Menu Bindings in the View List

View List: Visit View	Visit-Selected-View
View List: Remove View	Remove-Selected-View
View List: Visit New	Visit-File
View List: New Scratch	Scratch-View
View List: Exit-Editor	Quit

B.4 Additional Menu Bindings in the Help View

Help View: Describe	Document-Symbol
Help View: Visit Definition	Visit-Symbol-Definition
Help View: Apropos	Apropos-String
Help View: Reset	Reset-Help

B.5 Additional Menu Bindings in a Directory Editor

Dired: Visit	Dired-Visit
Dired: Visit Read Only	Dired-Visit-Read-Only
Dired: Mark	Dired-Mark-Selection
Dired: Unmark	Dired-Unmark-Selection
Dired: Delete marked files	Dired-Delete-Files
Dired: Mark backup files	Dired-Mark-Editor-Files
Dired: Reread directory	Revert-Object
Dired: Undo	Undo

B.6 Additional Menu Bindings in a Language-Based View (SIMPLE2)

Language: Analyze	Analyze-Changes
Variables: Show Declaration and Uses	Query-Simple2-Variable
Variables: Goto Declaration	Goto-Simple2-Variable-Declaration
Variables: Rename Variable	Rename-Simple2-Variable
View⇒Program Graph: With Node Names	Visit-Program-Graph-Name-View
View⇒Program Graph: With Operators	Visit-Program-Graph-Operator-View
View⇒Subgraph At Cursor: With Node Names	Visit-Program-Subgraph-Name-View
View⇒Subgraph At Cursor: With Operators	Visit-Program-Subgraph-Operator-View

B.7 Additional Menu Bindings in a Graphical View

Window: Toggle Global Image	Global-Image-Toggle
Window: Enlarge Global Image	Global-Image-Enlarge
Window: Shrink Global Image	Global-Image-Shrink
Window: Zoom In	Zoom-In
Window: Zoom Out	Zoom-Out
Window: Zoom All	Zoom-All

C Operand Level Bindings in a Language-Based View (SIMPLE2)

Level: "Character"

OPERAND LEVEL BINDINGS

<i>Oplevel-Cursor-Backward:</i>	Previous-Character
<i>Oplevel-Cursor-Forward:</i>	Next-Character
<i>Oplevel-Cursor-In:</i>	Next-Line
<i>Oplevel-Cursor-Out:</i>	Previous-Line
<i>Oplevel-Cursor-Search-Backward:</i>	Re-Search-Backward
<i>Oplevel-Cursor-Search-Forward:</i>	Re-Search-Forward
<i>Oplevel-Cursor-To-First:</i>	Move-To-Bos
<i>Oplevel-Cursor-To-Last:</i>	Move-To-Eos
<i>Oplevel-Cursor-To-Mouse:</i>	Cursor-To-Mouse
<i>Oplevel-Delete:</i>	Delete-Character
<i>Oplevel-Menu:</i>	Execute-Oplevel-Menu
<i>Oplevel-Mouse-Extend:</i>	Select-Region-Dot-To-Mouse
<i>Oplevel-Query-Replace-All:</i>	Query-Replace-All
<i>Oplevel-Replace-All:</i>	Replace-All
<i>Oplevel-Select:</i>	Deselect-Region

Level: "Word"

OPERAND LEVEL BINDINGS

<i>Oplevel-Cursor-Backward:</i>	Previous-Word
<i>Oplevel-Cursor-Forward:</i>	Next-Word
<i>Oplevel-Cursor-In:</i>	Next-Line
<i>Oplevel-Cursor-Out:</i>	Previous-Line
<i>Oplevel-Cursor-To-First:</i>	Move-To-First-Word
<i>Oplevel-Cursor-To-Last:</i>	Move-To-Last-Word
<i>Oplevel-Cursor-To-Mouse:</i>	Mouse-Select-Fullword
<i>Oplevel-Delete:</i>	Delete-Fullword
<i>Oplevel-Menu:</i>	Execute-Oplevel-Menu
<i>Oplevel-Mouse-Extend:</i>	Mouse-Extend-Oplevel-Text
<i>Oplevel-Select:</i>	Select-Fullword

Level: "Line"

OPERAND LEVEL BINDINGS

<i>Oplevel-Cursor-Backward:</i>	Previous-Line
<i>Oplevel-Cursor-Forward:</i>	Next-Line
<i>Oplevel-Cursor-In:</i>	Next-Line
<i>Oplevel-Cursor-Out:</i>	Previous-Line
<i>Oplevel-Cursor-Search-Backward:</i>	Re-Search-Backward
<i>Oplevel-Cursor-Search-Forward:</i>	Re-Search-Forward
<i>Oplevel-Cursor-To-First:</i>	Move-To-Bos
<i>Oplevel-Cursor-To-Last:</i>	Move-To-Last-Line
<i>Oplevel-Cursor-To-Mouse:</i>	Mouse-Select-Line
<i>Oplevel-Delete:</i>	Delete-Line
<i>Oplevel-Menu:</i>	Execute-Oplevel-Menu
<i>Oplevel-Mouse-Extend:</i>	Mouse-Extend-Selection-Full-Line
<i>Oplevel-Query-Replace-All:</i>	Query-Replace-All
<i>Oplevel-Replace-All:</i>	Replace-All
<i>Oplevel-Select:</i>	Select-Line

Level: "Lexeme"

OPERAND LEVEL BINDINGS

<i>Oplevel-Cursor-Backward:</i>	Prev-Lexeme
<i>Oplevel-Cursor-Forward:</i>	Next-Lexeme
<i>Oplevel-Cursor-Search-Forward:</i>	Lexeme-Search-Forward
<i>Oplevel-Cursor-To-First:</i>	First-Lexeme
<i>Oplevel-Cursor-To-Last:</i>	Last-Lexeme
<i>Oplevel-Cursor-To-Mouse:</i>	Mouse-Select-Lexeme
<i>Oplevel-Delete:</i>	Delete-Lexeme
<i>Oplevel-Menu:</i>	Execute-Oplevel-Menu
<i>Oplevel-Mouse-Extend:</i>	Mouse-Extend-Lexeme
<i>Oplevel-Query-Replace-All:</i>	Query-Replace-Lexemes
<i>Oplevel-Replace-All:</i>	Replace-Lexemes
<i>Oplevel-Select:</i>	Select-Lexeme

Level: "Expression"

OPERAND LEVEL BINDINGS

<i>Oplevel-Cursor-Backward:</i>	Prev-Oplevel-Node
<i>Oplevel-Cursor-Forward:</i>	Next-Oplevel-Node
<i>Oplevel-Cursor-In:</i>	In-Oplevel-Node
<i>Oplevel-Cursor-Out:</i>	Out-Oplevel-Node
<i>Oplevel-Cursor-To-First:</i>	First-Oplevel-Node
<i>Oplevel-Cursor-To-Last:</i>	Last-Oplevel-Node
<i>Oplevel-Cursor-To-Mouse:</i>	Mouse-Select-Oplevel-Node
<i>Oplevel-Delete:</i>	Delete-Oplevel-Node
<i>Oplevel-Menu:</i>	Execute-Oplevel-Menu
<i>Oplevel-Mouse-Extend:</i>	Mouse-Extend-Oplevel-Node
<i>Oplevel-Select:</i>	Select-Oplevel-Node

D Options Defined in *Pan*

Apropos-Documentation-Sub-Type-List	OPTION
Type: list	
Default Value: (:option-variable :command :view-style)	
Scopes: global	
If non-nil, the apropos commands list only symbols defined with a documentation sub-type in this list.	
Arrow-Mouse-Icon	OPTION
Type: dotted pair of strings	
Default Value: ("left_ptr" . "left_ptr")	
Scopes: view object view-style global	
Arrow mouse icon.	
Auto-Show-Match	OPTION
Type: boolean	
Default Value: t	
Scopes: view object view-style global	
If T, insert of a right bracket shows matching left bracket.	
Auto-Show-Match-Limit	OPTION
Type: integer	
Default Value: 2000	
Scopes: view object view-style global	
Bound on number of characters to scan when Auto-Show-Match is on.	
Autowrap-Search	OPTION
Type: boolean	
Default Value: t	
Scopes: view object view-style global	
If T, search wraps around at Eos back to cursor; else to Eos only.	
Backup-Object?	OPTION
Type: boolean	
Default Value: t	
Scopes: object global	
When true, the first time an object is saved, the original is backed up.	
Case-Sensitive-Lexeme-Search	OPTION
Type: boolean	
Default Value: nil	
Scopes: view object view-style global	
When attempting to perform regular expression matching on lexemes, should comparisons be case sensitive?	
Checkpoint-Modification-Interval	OPTION
Type: integer	
Default Value: 250	
Scopes: object global	
Checkpoint after this many modifications without saving or checkpointing.	

Clipboard-Max-Size	OPTION
Type: integer	
Default Value: 8	
Scopes: global	
Maximum number of clips in clipboard.	
Default-Line-Style	OPTION
Type: list	
Default Value: ("line-solid" "line-solid")	
Scopes: view object view-style global	
Default line style for objects displayed in graph window. Possible values are line-solid, line-on-off-dash or line-double-dash. All values are expressed as strings.	
Demo	OPTION
Type: boolean	
Default Value: nil	
Scopes: global	
Controls special configuration modes suitable for demos.	
Dired-Ls-Flags	OPTION
Type: string	
Default Value: "-a"	
Scopes: global	
String containing flags for /bin/ls command used in Directory Editor. The string must begin with the "-" prefix. The flag -l is supplied automatically, so need not be included. Any of the flags -acrFt may be used. Don't use any of the flags -dfgisR.	
Editor-File-Search-List	OPTION
Type: list	
Default Value: (". " "~" "/usr/local/lib/pan/")	
Scopes: global	
A list of directory names, specified as strings, to search when loading and requiring editor files. May include standard directory naming conventions like ".", "~", and "~user" where user must be a valid user name in the system. Used by Load-File, editor-load, and editor-require.	
Editor-Files-Pattern	OPTION
Type: string	
Default Value: ".#Pan."	
Scopes: global	
Regex pattern matching files created by Editor for backup and checkpointing.	
Fast-Draw-Color	OPTION
Type: dotted pair of strings	
Default Value: ("midnight blue" . "black")	
Scopes: view object view-style global	
Color to use when fast drawing outlines.	

Global-Image-Initial-Height	OPTION
Type: real	
Default Value: 0.2	
Scopes: view object view-style global	
Initial height of global image as percentage of the graph window height.	
Global-Image-Initial-On?	OPTION
Type: boolean	
Default Value: t	
Scopes: view object view-style global	
Determines whether global image is initially displayed.	
Global-Image-Initial-Width	OPTION
Type: real	
Default Value: 0.2	
Scopes: view object view-style global	
Initial width of global image as percentage of the graph window width.	
Global-Image-Outline-Color	OPTION
Type: dotted pair of strings	
Default Value: (" forest green " . " black ")	
Scopes: view object view-style global	
Color to use for box around global image.	
Graph-Window-Zoom-Factor	OPTION
Type: real	
Default Value: 0.1	
Scopes: view object view-style global	
Multiplier for zooming operations.	
Graphical-Tree-Hbox-Background-Color	OPTION
Type: dotted pair of strings	
Default Value: (" white " . " white ")	
Scopes: view object view-style global	
Background color for a horizontal box	
Graphical-Tree-Hbox-Border-Color	OPTION
Type: dotted pair of strings	
Default Value: (" midnight blue " . " black ")	
Scopes: view object view-style global	
Line color for a horizontal box	
Graphical-Tree-Hbox-Border-Style	OPTION
Type: dotted pair of strings	
Default Value: (" line-solid " . " line-solid ")	
Scopes: view object view-style global	
Line style for a horizontal box	

Graphical-Tree-Hbox-Border-Thickness	OPTION
Type: integer	
Default Value: 3	
Scopes: view object view-style global	
Line border for a horizontal box	
Graphical-Tree-Hbox-Text-Color	OPTION
Type: dotted pair of strings	
Default Value: ("black" . "black")	
Scopes: view object view-style global	
Text color for a horizontal box	
Graphical-Tree-Horiz-Node-Spacing	OPTION
Type: integer	
Default Value: 15	
Scopes: view object view-style global	
Horizontal spacing between parent and child nodes	
Graphical-Tree-Line-Arrow-Filled?	OPTION
Type: integer	
Default Value: 1	
Scopes: view object view-style global	
Directed edge arrow filled in?	
Graphical-Tree-Line-Arrow-Length	OPTION
Type: integer	
Default Value: 6	
Scopes: view object view-style global	
Directed edge arrow length	
Graphical-Tree-Line-Arrow-Width	OPTION
Type: integer	
Default Value: 4	
Scopes: view object view-style global	
Directed edge arrow width	
Graphical-Tree-Line-Color	OPTION
Type: dotted pair of strings	
Default Value: ("midnight blue" . "black")	
Scopes: view object view-style global	
Edge line color	
Graphical-Tree-Line-Style	OPTION
Type: dotted pair of strings	
Default Value: ("line-solid" . "line-solid")	
Scopes: view object view-style global	
Edge line style	

Graphical-Tree-Line-Thickness	OPTION
Type: integer	
Default Value: 2	
Scopes: view object view-style global	
Edge line thickness	
Graphical-Tree-Node-Border	OPTION
Type: integer	
Default Value: 4	
Scopes: view object view-style global	
Border ('whitespace') around a node	
Graphical-Tree-Node-Type	OPTION
Type: integer	
Default Value: 0	
Scopes: view object view-style global	
Symbolic constant for the drawing figure for nodes	
Help-View-At-Startup	OPTION
Type: boolean	
Default Value: t	
Scopes: global	
If non-nil, create an empty help view at startup.	
Highlight-Query-Results	OPTION
Type: boolean	
Default Value: t	
Scopes: view object view-style global	
When t , visually highlight text associated with all components resulting from the most recent structural query.	
Highlight-Semantic-Errors	OPTION
Type: boolean	
Default Value: t	
Scopes: view object view-style global	
When t , visually highlight the text associated with all components having unsatisfied semantic constraints.	
Highlight-Structure-Cursor	OPTION
Type: boolean	
Default Value: t	
Scopes: view object view-style global	
When t , visually highlight text associated with the structure cursor's location.	
Highlight-Syntax-Errors	OPTION
Type: boolean	
Default Value: t	
Scopes: view object view-style global	
When t , visually highlight the text associated with all components resulting from syntactic error recovery.	

Indent-With-Tabs	OPTION
Type: <code>boolean</code>	
Default Value: <code>nil</code>	
Scopes: <code>view object view-style global</code>	
If T, use tabs when performing computed indentations; else just spaces.	
Killring-Max-Size	OPTION
Type: <code>integer</code>	
Default Value: <code>16</code>	
Scopes: <code>view object view-style global</code>	
Maximum number of elements retained in kill-ring.	
Kills-To-Clipboard	OPTION
Type: <code>boolean</code>	
Default Value: <code>nil</code>	
Scopes: <code>view object view-style global</code>	
If true, kill commands use the global clipboard instead of the local kill-ring.	
Lisp-Mouse-Icon	OPTION
Type: <code>dotted pair of strings</code>	
Default Value: <code>("star" . "star")</code>	
Scopes: <code>view object view-style global</code>	
Lisp mouse icon.	
Load-Verbose	OPTION
Type: <code>boolean</code>	
Default Value: <code>t</code>	
Scopes: <code>global</code>	
When non-nil, Load-File, editor-load, and editor-require write messages to standard output.	
Modula2-Src-Dir	OPTION
Type: <code>boolean</code>	
Default Value: <code>nil</code>	
Scopes: <code>global</code>	
Directory containing source files for Modula2 standard modules. When present, semantic analysis imports information from them by visiting and analyzing imported modules.	
Object-Modified?	OPTION
Type: <code>boolean</code>	
Default Value: <code>nil</code>	
Scopes: <code>object</code>	
True when the current object is modified.	
Object-Protected?	OPTION
Type: <code>boolean</code>	
Default Value: <code>nil</code>	
Scopes: <code>object</code>	
True when the current object is protected.	

Operand-Level-Choices

OPTION

Type: **boolean**Default Value: **nil**Scopes: **view object view-style global**

A list of currently visible operand levels from which the user may select one to be "current". The default is the first in the list.

Package-Symbol-Names

OPTION

Type: **boolean**Default Value: **nil**Scopes: **global**

If non-nil, help and other tools will attempt to print symbol names with their packages when that package is not user. Otherwise, tools will usually not print package names.

Panel-Bg-Color

OPTION

Type: **dotted pair of strings**Default Value: ("**white**" . "**white**")Scopes: **view object view-style global**

Background color for window's panel.

Panel-Flag-Default-Bitmap

OPTION

Type: **string**Default Value: "**asterisk.12x12**"Scopes: **view object view-style global**

The default bitmap for panel flags. Assigning this variable does not affect current flags.

Panel-Flag-Default-Fg-Color

OPTION

Type: **dotted pair of strings**Default Value: ("**black**" . "**black**")Scopes: **view object view-style global**

The default foreground color for panel flags. Assigning this variable does not affect current flags.

Panel-Flags-Bg-Color

OPTION

Type: **dotted pair of strings**Default Value: ("**white**" . "**white**")Scopes: **view object view-style global**

Background color behind panel flags.

Panel-Logo-Bg-Color

OPTION

Type: **dotted pair of strings**Default Value: ("**white**" . "**white**")Scopes: **view object view-style global**

Background color for editor logo in panel.

Panel-Logo-Bitmap

OPTION

Type: **string**Default Value: "**pan-edit.31x22**"Scopes: **view object view-style global**

Bitmap that specifies the editor logo; appears at left of every panel.

Panel-Logo-Fg-Color Type: dotted pair of strings Default Value: ("black" . "black") Scopes: view object view-style global Foreground color for editor logo in panel.	OPTION
Panel-View-Logo-Bg-Color Type: dotted pair of strings Default Value: ("white" . "white") Scopes: view object view-style global Background color for view style logo in panel.	OPTION
Panel-View-Logo-Bitmap Type: string Default Value: "graph-logo.32x32" Scopes: view object view-style global Bitmap that specifies the view style logo: appears at next to panel logo.	OPTION
Panel-View-Logo-Fg-Color Type: dotted pair of strings Default Value: ("black" . "black") Scopes: view object view-style global Foreground color for view style logo in panel.	OPTION
Pause-Ticks Type: integer Default Value: 50000 Scopes: global Constant multiplier for Pause command.	OPTION
Prefix-Arg-Multiplier Type: integer Default Value: 4 Scopes: view object view-style global The multiplier value for prefix arguments.	OPTION
Print-Stats-On-Termination Type: boolean Default Value: nil Scopes: global Print statistics information on termination of Pan.	OPTION
Gc-Mouse-Icon Type: dotted pair of strings Default Value: ("box_spiral" . "box_spiral") Scopes: view object view-style global The mouse icon displayed during garbage collection.	OPTION

<p>Reticle-Outline-Color</p> <p>Type: dotted pair of strings</p> <p>Default Value: ("dark orange" . "black")</p> <p>Scopes: view object view-style global</p> <p>Color to use to show position of reticle.</p>	OPTION
<p>Scratch-View-At-Startup</p> <p>Type: boolean</p> <p>Default Value: nil</p> <p>Scopes: global</p> <p>If non-nil, create an empty scratch view at editor startup.</p>	OPTION
<p>Text-Fill</p> <p>Type: boolean</p> <p>Default Value: nil</p> <p>Scopes: view object view-style global</p> <p>Controls automatic line filling in text.</p>	OPTION
<p>Text-Line-Length</p> <p>Type: integer</p> <p>Default Value: 65</p> <p>Scopes: view object view-style global</p> <p>Max line length for text filling.</p>	OPTION
<p>Text-Window-Bg-Colormap</p> <p>Type: dotted pair of strings</p> <p>Default Value: (("white" . "white"))</p> <p>Scopes: view object view-style global</p> <p>Non-empty list of color specifications for text rendering background shading, where each specification is a dotted pair of color names, the first to be used when performing color rendering, the second to be used when performing monochrome rendering. Slot positions specify colors for (0) background 1, (1) background 2, (2) backgrounds 1 and 2 together. Due to a text viewport implementation restriction, text with null background is always white. Unspecified slots default to the first.</p>	OPTION
<p>Text-Window-Col-Popover</p> <p>Type: integer</p> <p>Default Value: 16</p> <p>Scopes: view object view-style global</p> <p>Minimum characters to move window when scrolling left/right.</p>	OPTION
<p>Text-Window-Empty-Line-Char</p> <p>Type: character</p> <p>Default Value: #\.</p> <p>Scopes: view object view-style global</p> <p>Character prefix for displaying empty lines in a text window.</p>	OPTION

Text-Window-Fg-Colormap OPTION

Type: dotted pair of strings

Default Value: (("black" . "black"))

Scopes: view object view-style global

Non-empty list of color specifications for text rendering ink colors, where each specification is a dotted pair of color names, the first to be used when performing color rendering, the second to be used when performing monochrome rendering. Slot positions specify ink colors 0 through 3. Unspecified slots default to the first.

Text-Window-Fontmap OPTION

Type: list

Default Value: ("fixed")

Scopes: view object view-style global

List of font specifications, where each font specification is either a single font name or a dotted pair of font names.

Text-Window-Init-Cols OPTION

Type: integer

Default Value: 78

Scopes: view object view-style global

Number of columns in a text window when created.

Text-Window-Init-Rows OPTION

Type: integer

Default Value: 30

Scopes: view object view-style global

Number of rows in a text window when created.

Text-Window-Proportional-Scroll OPTION

Type: boolean

Default Value: t

Scopes: view object view-style global

If T, vertical scroll moves proportional to distance between mouse and top of scrollbar, else fixed screenful at a time.

Text-Window-Row-Popup OPTION

Type: integer

Default Value: 4

Scopes: view object view-style global

Minimum number rows to move window when scrolling up/down.

Text-Window-Tabwidth OPTION

Type: integer

Default Value: 8

Scopes: view object view-style global

Number of characters to display for a tab character.

Think-Mouse-Icon	OPTION
Type: dotted pair of strings	
Default Value: ("watch" . "watch")	
Scopes: view object view-style global	
Think mouse icon.	
Undo-Size	OPTION
Type: integer	
Default Value: 20	
Scopes: object global	
The size of the undo history.	
Window-Alert-Style	OPTION
Type:	
Default Value: :bell	
Scopes: view object view-style global	
Style for alerting user. The only style currently supported is :bell.	
Window-Bg-Color	OPTION
Type: dotted pair of strings	
Default Value: ("alice blue" . "white")	
Scopes: view object view-style global	
Default background color of window.	
Window-Close-With-Icon	OPTION
Type: boolean	
Default Value: t	
Scopes: view object view-style global	
Determines if an icon is created when the window is closed.	
Window-Default-Mouse-Icon	OPTION
Type: dotted pair of strings	
Default Value: ("left_ptr" . "left_ptr")	
Scopes: view object view-style global	
Specifies the default mouse icon.	
Window-Icon-Name	OPTION
Type: string	
Default Value: "Untitled"	
Scopes: view object view-style global	
Title of icon representing the window.	
Window-Initial-Pixel-Height	OPTION
Type: integer	
Default Value: 500	
Scopes: view object view-style global	
Initial height, in pixels, of window.	

Window-Initial-Pixel-Width OPTION
Type: `integer`
Default Value: 500
Scopes: `view object view-style global`
Initial width, in pixels, of window.

Window-Initial-X-Position OPTION
Type: `integer`
Default Value: 0
Scopes: `view object view-style global`
Initial X position of top left hand corner of window.

Window-Initial-Y-Position OPTION
Type: `integer`
Default Value: 0
Scopes: `view object view-style global`
Initial Y position of top left hand corner of window.

Window-Message-History-Size OPTION
Type: `integer`
Default Value: 32
Scopes: `view object view-style global`
The number of window messages saved for reviewing.

Window-Name OPTION
Type: `string`
Default Value: "Untitled"
Scopes: `view object view-style global`
Title of window.

Window-Use-Color OPTION
Type: `boolean`
Default Value: `t`
Scopes: `view object view-style global`
If operating on a color monitor, then setting Window-Use-Color to `t` specifies that Pan is to use color settings.
If a monochrome monitor is being used, this option variable has no effect.

Zero-Index-Lines OPTION
Type: `boolean`
Default Value: `nil`
Scopes: `view object view-style global`
If `T`, arguments to Goto-Line are interpreted as 0-indexed, else 1-indexed.

E Flags Defined in *Pan*

Database-Updated?	FLAG
Presentation: "D"	
Behavior: gray when cleared	
Maps: On: D.12x12	
Off: gray-D.12x12	
Set when semantics of tree have been analyzed and database updated.	
Object-Modified?	FLAG
Presentation: "★"	
Behavior: invisible when cleared	
Maps: On: asterisk.12x12[firebrick]	
Off: no map	
True when the current object is modified.	
Object-Protected?	FLAG
Presentation: "Ⓔ"	
Behavior: invisible when cleared	
Maps: On: read-only.12x12	
Off: no map	
True when the current object is protected.	
Parse-Is-Current?	FLAG
Presentation: "∧"	
Behavior: gray when cleared	
Maps: On: tree.12x12	
Off: gray-tree.12x12	
Set when language file has been parsed.	
Semantic-Errors-Present?	FLAG
Presentation: "#"	
Behavior: invisible when cleared	
Maps: On: crosshatch.12x12	
Off: no map	
Nil if there are no semantic errors, the number of unsatisfied constraints if there are.	
Syntax-Errors-Present?	FLAG
Presentation: "!"	
Behavior: invisible when cleared	
Maps: On: exclamation-point.12x12	
Off: no map	
Nil if there are no parse errors, the number of error nodes if there are.	
Text-Fill	FLAG
Presentation: "↻"	
Behavior: invisible when cleared	
Maps: On: text-fill.12x12	
Off: no map	
Controls automatic line filling in text.	

F Character Sets in a Text View

filename-terminators Elements: (Tab)(Newline)(Space)\ Characters that terminate filenames in output from "ls".	CHARACTER SET
identifier-characters Elements: 0123456789ABCDEFGHIJKLMNOPQRSTUVWXYZabcdefghijklmnopqrstuvwxyz Identifier characters.	CHARACTER SET
indentation-characters Elements: (Tab)(Space) Indentation characters, a subset of whitespace-characters.	CHARACTER SET
match-characters Elements: ()[]{} The characters that are part of match pairs.	CHARACTER SET
whitespace-characters Elements: (Tab)(Newline)(Space) Whitespace characters.	CHARACTER SET
word-characters Elements: 0123456789ABCDEFGHIJKLMNOPQRSTUVWXYZabcdefghijklmnopqrstuvwxyz Word characters.	CHARACTER SET

G View-Styles

base-view-style The View List style.	VIEW STYLE
database-view-style The Colander database view style.	VIEW STYLE
dired-view-style The Directory Editor view style.	VIEW STYLE
help-view-style The Help View style.	VIEW STYLE
lex-data-view-style The Lexical stream internal data view	VIEW STYLE
node-sem-view-style The node semantics view style.	VIEW STYLE
null-view-style A null view style for the View List class.	VIEW STYLE
program-subgraph-style Graphically presents a subtree of the internal tree representation for programs	VIEW STYLE
program-graph-style Graphically presents the internal tree representation of programs	VIEW STYLE
subtree-data-view-style The internal data for the subtree representation view	VIEW STYLE
text-edit-view-style The view style for ordinary text editing.	VIEW STYLE
tree-data-view-style The internal data for the tree representation view	VIEW STYLE
worklist-view-style The Colander worklist view style.	VIEW STYLE

Index

- active view 2
- active window 2
- :add 54
- add-variable-notifier 57, 58
- analysis
 - incremental 12, 36
- Analyze 36, 74
- Analyze-Changes 36
- Announce-Option-Variable 10, 52, 53
- Announce-Structure-Cursor-Info 38, 40
- Announce-Structure-Cursor-Node-Rule 38
- Announce-Structure-Cursor-Node-Rule 40
- Announce-Text-Cursor-Info 22
- Any Structure Level 40, 41
- Append Selection To ... 19, 72, 73
- Append-Selection-To-File 19
- Apropos- 16
- Apropos 16
- Apropos 16, 72, 73, 74
- Apropos-Documentation-Sub-Type-List 77
- Apropos-String 16
- argument
 - numeric 13
 - text 13, 14
 - tree node 39
- Arrow-Mouse-Icon 77
- Auto-Exec 17, 38, 46, 47, 60
- Auto-Load 17, 38, 46, 47, 60
- Auto-Show-Match 33, 77
- Auto-Show-Match-Limit 77
- Autowrap-Search 32, 77
- backup
 - revert 20
- backup 19, 20
- Backup-Object 19
- Backup-Object? 20, 77
- Backward-Expr 33
- Backward-Vscroll-Current-Window 20, 21
- balanced bracket expression 33
- base-view-style 91
- binding 2, 48, 7
- bindings
 - scope 48
 - typographic format 12
- Bind-Key 48
- Bind-Menu 50
- Bind-Oplevel-Command-List 51
- Bind-Oplevel-Menu 51, 52
- break loop 13, 22
- :buffer 7
- By Command 16, 51, 72, 73
- By Level 16, 51, 72, 73
- cancel 14
- Capitalize-Selection 31
- Capitalize-Word 31
- case
 - change 31
- case sensitive 43
- Case-Sensitive-Lexeme-Search 43, 77
- center 27
- Center-Line 27
- Char. Sets 16, 72, 73
- character set
 - alter 54
 - create 54
- character set 10, 33, 54
- character sets 2
- Character Sets 54
- Character operand level 9, 22-26, 28, 29, 32, 40, 64, 75
- checkpoint
 - revert 20
- checkpoint 20
- Checkpoint-Modification-Interval 20, 77
- Checkpoint-Object 19
- Clear-Structure-Cursor 38, 40
- clipboard
 - copy 30
 - cut 30
 - numeric argument 30
 - paste 30
 - replace 30
 - size 30
 - viewing 30
- clipboard 16
- clipboard 30
- Clipboard 30
- clipboard 31, 43, 6
- Clipboard 72, 73
- Clipboard-Max-Size 6, 30, 78
- Close 20, 72, 73
- Close-Current-Window 20

- c-mode 46
- c-mode.cl 46
- c-mode.fasl 46
- .col 11
- Colander 1, 11, 12, 34, 36, 37, 44, 45, 46, 65, 66
- color representation 54
- command 13
 - cancel 14
 - execution
 - by keystroke 7
 - by menu 8, 13
 - by name 13
 - by operand level 9
 - package 47
 - undo 15
- Command -> Key 16, 72, 73
- command arguments 13
- Command 12
- Commands Available 16, 72, 73
- comment 37
- configuration 4, 8, 11, 45
 - language-based 46
- consistent information 37
- constant 37
- :cont 13
- contextual constraints 12, 37
- control character insertion 27
- Copy To Cursor 31, 72, 73
- Copy 30, 72, 73
- Copy-Menu 50
- Copy-Selection-As-Kill 29, 30
- Copy-Selection-To-Cursor 30, 31
- Copy-To-Clipboard 30, 49
- Create-Menu 50
- current operand level 9, 25
- cursor 22
 - effects of scrolling 21
 - information 22
 - location 24
 - motion 24, 33, 41
 - move to line 24
- cursor motion 5, 25
 - numeric argument 23
- Cursor-Backward 9, 23, 41
- Cursor-Forward 8, 9, 23, 41, 62, 64
- Cursor-In 9, 23, 41
- Cursor-Out 9, 23, 41
- Cursor-Search-Backward 9, 32
- Cursor-Search-Forward 9, 32, 43
- Cursor-To-First 9, 23, 41
- Cursor-To-Last 9, 24, 41
- Cursor-To-Mouse
- Cursor-To-Mouse 9, 22, 26, 40, 49, 75
- Cursor-To-Token 38, 40
- customization 45
- Cut 30, 72, 73
- cut-and-paste operations 6
- Cut-To-Clipboard 30, 49
- Cycle and Show 30, 72, 73
- Cycle-Clipboard 30
- Cycle-Kill 29, 30
- Cycle-Paste 30
- Cycle-Paste-Clipboard 30
- Cycle-Show-Clipboard 30
- Cycle-Show-Kill 29, 30
- Cycle-Yank 29, 30
- Database-Updated? 36, 37, 65, 89
- database-view-style 91
- Debug 16
- debugging
 - graphical views 44
 - navigation commands 45
 - textual views 44
- Declaration 10, 38
- default configuration 7
- default font 11, 37
- Default Menu 16, 50, 72, 73
- default menu 8
- default scope 47
- Default-Line-Style 78
- Define-Command 60
- Define-Hook 57, 62
- Define-Hook-Function 57, 58, 62
- Define-Option-Variable 57, 64
- Define-Variable 57, 64
- Delete marked files 18, 74
- delete 25, 29
- Delete 28
- :delete 54
- Delete 8, 9, 62, 64
- Delete-Blank-Lines 28, 29
- Delete-Character 28, 29, 48, 75
- Delete-Fullword 28, 29, 75
- Delete-Horizontal-Space 28, 29
- Delete-Indentation 28, 29
- Delete-Lexeme 76
- Delete-Line 28, 75
- Delete-Oplevel-Node 76

- Delete-Previous-Character 28, 29, 49
- Delete-Previous-Word 28, 29
- Delete-Region-Dot-To-Mark 28, 29
- Delete-Selected-Region 28, 29
- Delete-Word 28, 29
- deletion
 - recover 29
- Demo 78
- derived information 37
- Describe 16, 74
- Describe-Selection 16
- deselect 5
- Deselect-Region 26, 27, 75
- directory
 - edit 18, 19
- directory editor 18, 19
- directory 18, 19
- dired 18, 19
- Dired 18, 19, 74
- Dired-Delete-Files 18, 19
- Dired-Ls-Flags 78
- Dired-Mark-Editor-Files 19
- Dired-Mark-Selection 18, 19
- Dired-Unmark-Selection 18
- dired-view-style 4, 47, 91
- Dired-Visit 18, 19
- Dired-Visit-Read-Only 18, 19
- Display All 16, 48, 72, 73
- Display- 17
- Display-All-Key-Bindings 16, 48
- Display-Apropos-Index 16
- Display-Auto-Exec 16, 46
- Display-Auto-Load 16, 46
- Display-Bug-Report-Info 17
- Display-Char-Set-Documentation 17, 54
- Display-Char-Sets 10, 16, 54
- Display-Command-Documentation 17
- Display-Commands 16
- Display-Configuration 17
- Display-Constant-Documentation 17
- Display-Default-Menu 16, 50, 8
- Display-File-Ids 17
- Display-Flags 16, 55
- Display-Function-Documentation 17
- Display-Hook-Documentation 17, 57
- Display-Hooks 17, 57
- Display-Key-Binding 16
- Display-Key-Bindings-For-Command 16
- Display-Language-List 16, 46

- Display-Macro-Documentation 17
- Display-Notifiers 17, 57
- Display-Objects 16
- Display-Operand-Command-Bindings 16, 51
- Display-Operand-Command-Documentation 17, 51
- Display-Operand-Level-Bindings 16, 51
- Display-Operand-Level-Documentation 17, 51
- Display-Operand-Level-Menus 16, 51
- Display-Option-Documentation 17, 51, 53
- Display-Option-Variables 10
- Display-Option-Variables 16, 52, 17
- Display-Version 16
- Display-View-Class-Key-Bindings 17
- Documentation 17
- Document-Symbol 16, 50
- Dot 61
- Dot-To-Mark 24
- edit
 - protected 19, 20
- edit window 4
- editing area 3, 4
- editing context 7
- editing interface 11
- Editor-Error 14
- Editor-File-Search-List 46, 78
- Editor-Files-Pattern 78
- End-Of-Word 24
- Enlarge Global Image 33, 74
- error
 - highlighting 37, 42
 - lexical 42
 - semantic 42
 - syntax 42
- error handling 12
- Execute-Command 13, 48, 56, 57
- Execute-Lisp 56, 57
- Execute-Lisp-Line 48
- Execute-Menu 13, 49, 8
- Execute-Oplevel-Menu 51, 52, 75, 76
- exit *Pan* 13, 22
- Exit-Editor 13, 19, 74
- expression
 - kill 29
 - selection 27
- Expression 10, 38, 39, 40, 41, 76
- expression 54
- Fast-Draw-Color 78
- file
 - auto-load 46

- backup 19, 20
- delete 19
- edit 18, 19
- insert 27
- load 46, 57
- mark 19
- revert 20
- File 19, 27, 72, 73, 73
- Filename Auto-Exec Map 16, 46, 72, 73
- Filename Auto-Load Map 16, 46, 72, 73
- filename-terminators 90
- fill 28
 - multiple lines 28
 - numeric argument 28
 - prefix 28
- filling text 28
- Fill-Selected-Lines 28
- First-Lexeme 41, 76
- First-Non-Blank 24
- First-Oplevel-Node 41, 76
- flag is set 10
- flag 2, 10
- Flags 16, 55, 72, 73
- font 37
- font code 11, 37
- font map 11, 53
 - scope 11
- formal language 34
- Forward-Expr 33
- Forward-Vscroll-Current-Window 20, 21
- Full-Line 27
- Fullword 27
- function keys 8
- Gc-Mouse-Icon 84
- generic command 25
- generic operations 8
- global bindings 7
- global image
 - resize 6, 34
 - toggle 6, 34
- global image 6, 34
- global values 17
- :global 7, 8, 10, 47, 48, 53
- Global 52, 72, 73
- Global-Image-Enlarge 33, 34
- Global-Image-Initial-Height 79
- Global-Image-Initial-On? 79
- Global-Image-Initial-Width 79
- Global-Image-Outline-Color 79
- Global-Image-Shrink 33, 34
- Global-Image-Toggle 33, 34
- Goto Declaration 74
- Goto-Line 24
- graph node
 - contents 33
- graphical representation 44
- graphical view
 - mouse buttons 34
 - navigation 6
 - scroll 34
 - subgraph 6
 - zoom 34
- graphical view 1, 6, 33, 44
- graphical window 4
- Graphical-Tree-Hbox-Background-Color 79
- Graphical-Tree-Hbox-Border-Color 79
- Graphical-Tree-Hbox-Border-Style 79
- Graphical-Tree-Hbox-Border-Thickness 80
- Graphical-Tree-Hbox-Text-Color 80
- Graphical-Tree-Horiz-Node-Spacing 80
- Graphical-Tree-Line-Arrow-Filled? 80
- Graphical-Tree-Line-Arrow-Length 80
- Graphical-Tree-Line-Arrow-Width 80
- Graphical-Tree-Line-Color 80
- Graphical-Tree-Line-Style 80
- Graphical-Tree-Line-Thickness 81
- Graphical-Tree-Node-Border 81
- Graphical-Tree-Node-Type 81
- Graph-Window-Zoom-Factor 33, 79
- *. [hc] 46
- help 15
- Help 15, 16, 17, 46, 48, 50, 51, 52, 54, 55, 72, 73
- help commands 16
- help view 2, 15, 30
- Help View 15, 16, 74
- Help-View-At-Startup 81
- help-view-style 4, 53, 91
- highlight color 39, 42
- Highlight-Query-Results 42, 81
- Highlight-Semantic-Errors 42, 81
- Highlight-Structure-Cursor 39, 42, 81
- Highlight-Syntax-Errors 42, 81
- hook 58
- How To Report Bugs 17, 72, 73
- icon 3, 20
- identifier 37
- identifier-characters 90
- implicit selection 5, 26

- delete 29
- kill 29
- inconsistent 37
- inconsistent information 37
- indent 27
- indentation
 - delete 29
- indentation-characters 10
- indentation-characters 90
- Indent-Like-Previous-Line 27
- Indent-With-Tabs 82
- information panel 3, 4, 22, 25, 40, 42
- In-Oplevel-Node 41, 76
- Insert Text from... 27, 72
- Insert-File 27
- Insert-Newline 27
- Insert-Newline-Fill 28, 49
- Insert-Parentheses 27
- Insert-Space-Fill 28, 49
- internal state 20
- internal structural representation 12
- internal tree representation 6, 33, 39, 44, 45
- Interrupt-Editor 13
- Just-One-Space 28, 29
- Key -> Command 16, 72, 73
- key binding
 - create 48
 - scope 8
- key binding 7, 48
 - typographic format 12
- key sequence 7, 48
- Keys 16, 48, 72, 73
- keyword 37
- kill 6, 29
 - expression 33
 - restore 30
- Kill- 6
- Kill 29
- Kill 29, 72, 73
- kill ring 6, 29, 43
 - cycle 30
 - size 30
 - view 30
- Kill-Expr 29, 33
- Kill-Previous-Word 29
- Kill-Region-Dot-To-Mark 29
- Killring-Max-Size 6, 30, 82
- Kill-Selected-Region 29
- Kills-To-Clipboard 6, 30, 62, 82
- Kill-To-Eol 29
- Kill-Word 29
- Ladle 1, 11, 12, 34, 38, 42, 44, 45, 46, 58
- language
 - load 46
 - operand levels 38
- language definition 11, 45
- language description 38
- Language Descriptions Loaded 16, 46, 72, 73
- language descriptions 11
- language view
 - flags 36
- Language 35, 36, 74
- language-based editing
 - text 35
- languages
 - and font use 37
- Last-Lexeme 41, 76
- Last-Oplevel-Node 41, 76
- Left-Hscroll-Current-Window 20, 21
- lex-data-view-style 91
- Lexeme 38, 39, 40, 41, 43, 76
- lexemes 37
- Lexeme-Search-Forward 43, 76
- lexical analysis 37, 42
- lexical errors 42
- line length 28
- line number 24
- line prefix 28
- Line operand level 22-24, 26, 28, 32, 75
- Lisp 57
- Lisp-Mouse-Icon 82
- Load-File 45, 46, 56, 57
- Load-From-Selection 45, 46, 56, 57
- Load-From-Text-Stream 45, 46, 56, 57
- Load-Verbose 82
- local bindings 7
- Lowercase-Selection 31
- Lowercase-Word 31
- mark
 - set 24
- Mark backup files 19, 74
- mark stack 5, 6, 24, 26
- Mark 18
- mark 6, 24, 26
- Mark 74
- match characters 27, 33, 54, 55, 90
- menu
 - scope 8

- menu bindings 8, 50
 - typographic format 12
- menu description 50
- menu item 8, 50
 - binding 8
- menu selection 4, 8
- Menu 51
- menus 4
- Menus 8
- MenuTitle 12, 8
- message
 - review 15
- message history 15
- message line 2, 4, 15, 21
- minor mode 47
- modifier keys 7
- Modula-2 34
- Modula2-Src-Dir 82
- Most Operand Levels 51
- mouse buttons
 - selection 4, 5
- mouse buttons 4, 8, 21, 22, 25, 26, 34, 41
- mouse 22
- Mouse-Extend 9, 26, 40
- Mouse-Extend-Lexeme 40, 76
- Mouse-Extend-Oplevel-Node 40, 76
- Mouse-Extend-Oplevel-Text 26, 75
- Mouse-Extend-Selection-Full-Line 26, 75
- Mouse-Extend-Selection-Fullword 26, 27
- Mouse-Select-Full-Line 26
- Mouse-Select-Fullword 22, 26, 27, 75
- Mouse-Select-Lexeme 40, 76
- Mouse-Select-Line 22, 26, 75
- Mouse-Select-Oplevel-Node 40, 76
- Mouse-Select-Word 26
- Move To Cursor 31, 72, 73
- Move-Selection-To-Cursor 31
- Move-To-Bol 24
- Move-To-Bos 23, 24, 75
- Move-To-Eol 24
- Move-To-Eos 24, 75
- Move-To-First-Word 23, 75
- Move-To-Last-Line 24, 75
- Move-To-Last-Word 24, 75
- naming conventions 12, 37
- New Scratch 18, 74
- Newline-And-Indent 27, 49
- Next- 23
- Next-Character 23, 57, 64, 75, 9
- Next-Lexeme 41, 76
- Next-Line 14, 23, 75
- Next-Line-Select 26, 27
- Next-Message-Current-Window 14
- Next-Oplevel-Node 41, 76
- Next-Word 23, 75
- node 44
- Node 41, 45
- node-sem-view-style 91
- notifier 58
- Null-Select 26, 27
- null-view-style 91
- Number-Of-Views-Created 57, 58
- numeric prefix 13, 14
- Object-Modified? 4, 10, 20, 82, 89
- Object-Protected? 4, 20, 82, 89
- Objects Being Viewed 16, 72, 73
- Open Another 20, 72, 73
- Open-Another-Window-In-View 20
- Open-A-Window-In-View 20
- Open-Line 27
- Operand Cmds. 16, 51, 72, 73
- operand level 2, 9, 22, 25, 39, 40, 41, 43
 - and selection 26
 - commands 25
 - current 25
 - delete 25, 29
 - error levels 41
 - language 38, 38
 - menu 38, 41
 - navigation 41
 - search 32, 43
 - select 22, 25, 26
 - selection by menu 25
 - selection 40
 - set 25
- operand level bindings 8, 25, 51
 - scope 10
 - command 51
 - menu 52
 - typographic format 12
- operand level menu 25, 52
- Operand Menus 16, 51, 72, 73
- OperandLevel 10, 12
- operand-level 2
- Operand-Level-Choices 38, 64, 83
- Operation 10
- Oplevel- 10, 41, 51
- Oplevel 38

- Oplevel-Cursor-Backward 23, 25, 41, 45, 49
- Oplevel-Cursor-Forward 9, 22, 23, 25, 40, 41, 45, 49
- Oplevel-Cursor-In 23, 25, 41, 45
- Oplevel-Cursor-Out 23, 25, 41, 45
- Oplevel-Cursor-Search 32
- Oplevel-Cursor-Search-Backward 25, 32
- Oplevel-Cursor-Search-Forward 25, 31, 49
- Oplevel-Cursor-To-First 23, 25, 41, 49
- Oplevel-Cursor-To-Last 23, 25, 41, 49
- Oplevel-Cursor-To-Mouse 22, 25, 26, 40, 41, 49
- Oplevel-Delete 25, 28, 29, 43
- Oplevel-In 41, 49
- Oplevel-Menu 9, 25, 38, 41, 49, 51, 52, 64
- Oplevel-Mouse-Extend 25, 26, 40
- Oplevel-Out 41, 49
- Oplevel-Query-Replace-All 25, 32
- Oplevel-Replace 32
- Oplevel-Replace-All 25, 32
- Oplevel-Select 25, 26, 40
- option
 - announce 53
 - define 57
 - set 53
- Option variables 10
- option 2, 10, 53
- :option 57
- Options 16, 51, 52, 72, 73
- Out-Oplevel-Node 41, 76
- package 47
- Package-Symbol-Names 48, 83
- Pan 16, 17, 46, 72, 73
- Panel- 54
- Panel-Bg-Color 53, 83
- Panel-Flag-Default-Bitmap 55, 83
- Panel-Flag-Default-Fg-Color 53-55, 83
- Panel-Flags-Bg-Color 53, 55, 83
- Panel-Logo-Bg-Color 53, 83
- Panel-Logo-Bitmap 83
- Panel-Logo-Fg-Color 53, 84
- Panel-View-Logo-Bg-Color 54, 84
- Panel-View-Logo-Bitmap 84
- Panel-View-Logo-Fg-Color 54, 84
- .panrc 1, 45-48, 53, 55, 57
- parentheses 27
- Parse-Is-Current? 36, 37, 66, 89
- Paste 30, 72, 73
- Paste-From-Clipboard 30, 49
- pattern match 32, 43
- Pause-Ticks 33, 84
- Perform-Hook 57, 62
- Panerrors 21
- Placeholder 38
- Pop-Mark 24
- pop-up window 14
- prefix
 - repetition 14
- prefix keys 7
- Prefix 13, 14
- Prefix-Arg-Multiplier 14, 84
- Preserve-All-Objects 19
- Previous- 23
- Previous-Character 23, 75
- Previous-Line 23, 75
- Previous-Line-Select 26, 27
- Previous-Word 23, 75
- Prev-Lexeme 41, 76
- Prev-Message-Current-Window 14
- Prev-Oplevel-Node 41, 76
- Print-Stats-On-Termination 84
- program
 - editing
 - language-based editing 34
 - operand levels 38
- Program Graph 35, 44, 74
- program-graph-style 91
- program-subgraph-style 91
- prompt 13, 14
- protected 19
- Protected-Visit-File 17
- < language >-mode 46
- < language >-mode.c1 12, 46
- Push-Mark 24
- query 43
- Query 38, 43
- Query-Replace-All 9, 15, 32, 43, 75
- Query-Replace-Lexemes 43, 76
- Quit 13
- quitting *Pan* 13
- Quote-Character 27
- Quote-Insert 27
- reanalysis 37, 44
- Rebind-Menu 50, 51
- Redo 15
- Redo 15, 72, 73
- Redraw 20, 72, 73
- Redraw-Current-Window 20
- reduction rule 40
- region 5

- regular expression 31, 32, 43
- Remove View** 74
- Remove-** 18
- Remove** 18, 72, 73
- Remove-Object** 18
- Remove-Selected-View** 18
- Remove-View** 18
- Rename Variable** 74
- Rename-View** 18
- replace 32
- Replace** 25, 32
- Replace-** 65
- Replace-All**
- Replace-All** 9, 15, 32, 43, 75
- Replace-From-Clipboard** 30
- Replace-Lexemes** 43, 76
- Reread directory** 19, 74
- Re-Search-Backward** 32, 75
- Re-Search-Forward** 31, 32, 75
- Reset Help** 15
- Reset** 74
- Reset-Help** 15, 16
- Reticle-Outline-Color** 85
- Revert** 19
- Revert** 72
- Revert** 73
- Revert-Object** 19
- Revert-Object-To-Backup** 19, 20, 60
- Revert-Object-To-Checkpoint** 19, 20, 60
- Right-Hscroll-Current-Window** 20, 21
- ring 5
 - cycle 5
- Save Copy As ...** 19, 72, 73
- save 13
- Save** 19, 72, 73
- Save-Object** 19
- Save-Object-Copy-As** 19
- scope 7, 47
- Scope** 47
- scoped values 17
- scratch view 18
- **scratch**** 18
- Scratch-View** 18
- Scratch-View-At-Startup** 85
- scroll 5, 21
 - horizontal 3, 21
 - numeric argument 21
 - proportional 21
 - vertical 21
 - with keyboard 21
 - with mouse 21
- scroll bars 2, 4
- scroll bubble 21
- Scroll To Cursor** 21, 72, 73
- Scroll-To-Cursor-Current-Window** 21
- Scroll-To-Cursor-Current-Window** 5
- search 32
 - cancel 32
 - numeric argument 32
 - operand level
 - numeric argument 32
 - replace 32
 - same expression 32
 - wrapped 32
- Search** 25
- search path 46
- select 4, 22, 25
 - expression 33
- Select** 9, 26, 40
- selected region 5
- Select-Expr** 26, 27, 33
- Select-Full-Line** 26, 27
- Select-Fullword** 26, 75
- selection 5, 13, 26
 - and operand level 26
 - and structure cursor 39
 - copy 31
 - deselection 27
 - language-based 40
 - load 57
 - move 31
 - numeric prefix 27
 - set 26
 - write 19
- selection is set 5
- SelectionName** 8, 12
- Select-Lexeme** 40, 76
- Select-Line** 26, 27, 75
- Select-Oplevel-Node** 40, 76
- Select-Region-Dot-To-Mark** 5, 26
- Select-Region-Dot-To-Mouse** 26, 49, 75
- Select-Text-Stream** 26, 27
- Select-Word** 26, 27
- Self-Insert** 27, 28, 49
- semantic analysis 37, 42
- semantic database 36
- semantic description 11
- semantic errors 42

- semantic information 12
- Semantic-Errors-Present? 36, 42, 89
- Set Option 52, 72, 73
- Set- 53
- Set-Buffer-Option-Variable 52
- Set-Char-Match 54, 55
- Set-Char-Set 54
- Set-Global-Option-Variable 52
- Set-Mark 24
- Set-Oplevel- 38
- Set-Oplevel-To-Character 24, 64
- Set-Oplevel-To-Declaration 64
- Set-Oplevel-To-Lexeme 38
- Set-Oplevel-To-Line 24
- Set-Oplevel-To-Node 38
- Set-Oplevel-To-Query 38
- Set-Oplevel-To-Semantic-Error 38
- Set-Oplevel-To-Syntactic-Error 38
- Set-Oplevel-To-Word 24
- Set-Text-Fill-Prefix 28
- Set-Text-Line-Length 28
- Set-View-Option-Variable 52
- Set-View-Style-Option-Variable 52
- Set-Working-Directory 18
- shadow 48
- :shadow 54
- Show Contents 30, 72, 73
- Show Declaration and Uses 74
- Show-Clipboard 30
- Show-Kill 29, 30
- Show-Match 33
- Shrink Global Image 33, 74
- Split-Line 27
- starting *Pan* 13
- start-up 45
- Statement 10, 38, 40
- Store 17, 19, 72, 73
- structural annotations 12
- structural navigation 41
- structural cursor 6, 39, 40, 41
 - and selection 39
 - clear 40
 - set 39
 - set 40
- structure node 40
- Subgraph At Cursor 35, 44, 74
- subgraph 44
- Sub-Redo 15
- Sub-Redo 15, 72, 73
- subtree 6
- subtree-data-view-style 91
- Sub-Undo 15, 32
- Sub-Undo 15, 72, 73
- Swap-Dot-And-Mark 24
- Syntactic analysis 37
- Syntactic Error 38
- syntactic errors 12, 42
- syntax analysis 42
- syntax description 11
- Syntax Error 41
- Syntax-Errors-Present? 36, 42, 89
- .tex 18
- tex-mode 47
- tex-mode.cl 47
- text
 - copy 30, 31
 - delete 29, 30
 - editing 22
 - fill 28, 3
 - kill 29
 - move 30, 31
 - replace 30
 - transposing 31
 - yank 30
- Text 50
- text color 42, 43
- text cursor 2, 3, 5, 26
- Text Edit 19, 27, 29, 31, 72, 73
- text insertion
 - numeric prefix 27
- text insertion 27
- text stream
 - load 57
- text view 1
- text window 4
- text-based editing 4
- text-edit-view-style 4, 46, 91
- Text-Fill 3, 4, 28, 85, 89
- Text-Fill-To-Blank-Line 28
- Text-Line-Length 27, 28, 61, 85
- textual argument 13
- textual insertion 5
- textual selection 26
- textual view 4, 22, 26, 46
- Text-Window-Bg-Colormap 39, 42, 53, 54, 85
- Text-Window-Col-Popover 85
- Text-Window-Empty-Line-Char 85
- Text-Window-Fg-Colormap 42, 43, 53, 54, 86

- Text-Window-Fontmap 11, 53, 61, 86
- Text-Window-Init-Cols 86
- Text-Window-Init-Rows 86
- Text-Window-Proportional-Scroll 21, 86
- Text-Window-Row-Popup 86
- Text-Window-Tabwidth 86
- Think-Mouse-Icon 87
- This View 16, 17, 48, 50, 51, 51, 52, 54, 55, 72, 73
- Toggle Global Image 33, 74
- Toggle Protection 19, 72, 73
- Toggle-Object-Modification 19, 20
- Toggle-Object-Protection 19, 20
- Toggle-Text-Fill 28
- Transpose-Characters 31
- Transpose-Characters-At-Cursor 31
- Transpose-Lines 31
- tree navigation 45
- tree-data-view-style 91
- Tree-Down 45
- Tree-Left 45
- Tree-Right 45
- Tree-Up 45
- type checking 12, 37
- unanalyzed text 37
- undo 15
 - numeric argument 15
- Undo 15, 27, 29, 32, 49, 72, 73
- Undo 15, 72, 73, 74
- Undo-Size 15, 87
- Unmark 18, 74
- Unsatisfied Constraint 38, 41
- unsatisfied constraints 12
- Uppercase-Selection 31
- Uppercase-Word 31
- user interface 7, 12
- variable 10
 - query 43
- Variables 35, 74
- Version 16, 72, 73
- :view 7, 8, 10, 46, 48
- view 1, 2, 7, 17, 34
 - create 18, 19
 - edit 18
 - graphical 44
 - remove 18
 - rename 19
 - save all 19
 - save 13, 19
 - scratch 18
 - subgraph 44
 - text 4, 22
 - visit 18
 - write 19
- View 18, 35, 44, 72, 73, 74
- view list 2, 3, 13, 18, 20
- View List 13, 17, 18, 74
- view name 2
- View Only 52, 72, 73
- View Style 52, 72, 73
- view style 4, 8
- :view-style 7, 8, 10, 47, 48, 53
- visit 19
- Visit 18, 74
- Visit Definition 16, 74
- Visit New... 17, 72, 73, 74
- Visit Read Only 18, 74
- Visit View 17, 18, 74
- Visit-And-Check-File 36, 37
- Visit-Backup 17, 60
- Visit-Checkpoint 17, 20, 60
- Visit-Database-View 44, 45
- Visit-Directory 18, 19
- Visit-File 17, 18, 37, 60
- Visit-Help-View 15, 16, 49
- Visit-Lexeme-Internal-Data-View 44
- Visit-Node-Semantics-View 44, 45
- Visit-Program-Graph- 44
- Visit-Program-Graph-Address-View 44
- Visit-Program-Graph-Context-View 44
- Visit-Program-Graph-Operator-View 44
- Visit-Program-Graph-Parse-Change-View 44
- Visit-Program-Graph-Parse-Status-View 44
- Visit-Program-Graph-View 44
- Visit-Program-Subgraph- 39, 44
- Visit-Program-Subgraph-Address-View 44
- Visit-Program-Subgraph-Context-View 44
- Visit-Program-Subgraph-Operator-View 44
- Visit-Program-Subgraph-Parse-Change-View 44
- Visit-Program-Subgraph-Parse-Status-View 44
- Visit-Program-Subgraph-View 44
- Visit-Selected-View 17, 18
- Visit-Subtree-Internal-Data-View 44, 45
- Visit-Symbol-Definition 16
- Visit-Tree-Internal-Data-View 44, 45
- Visit-View 18
- Visit-View-List 18, 49
- Visit-Worklist-View 44, 45
- white space

- delete 29
- whitespace-characters 90
- window 2, 17, 20
 - close 3, 20
 - redraw 20, 21
 - reopen 3, 20
- Window 5, 20, 21, 33, 72, 73, 74
- window manager 3, 20
- Window-Alert-Style 87
- Window-Bg-Color 87
- Window-Close-With-Icon 3, 20, 53, 87
- Window-Default-Mouse-Icon 63, 87
- Window-Icon-Name 87
- Window-Initial-Pixel-Height 87, 88
- Window-Initial-X-Position 88
- Window-Initial-Y-Position 88
- Window-Message-History-Size 15, 88
- Window-Modify-Flag-Collection 55
- Window-Name 88
- windows
 - multiple 20
- Window-Use-Color 54, 88
- With Node Names 44, 74
- With Operators 44, 74
- With-Buffer-Scope 47
- With-View-Scope 47
- With-View-Style-Scope 47, 53
- Word operand level 22-24, 26, 28, 32, 52, 75
- word-characters 10, 54, 90
- word-oplevel-menu 52
- worklist-view-style 91
- write protection 20
- Write Selection To ... 19, 72, 73
- Write-Selection-To-File 19
- yank 6
- Yank 29, 72, 73
- Yank-From-Kill-Ring 29, 30
- Zero-Index-Lines 24, 88
- zoom 33
 - numeric argument 34
- Zoom All 33, 74
- Zoom In 33, 74
- Zoom Out 33, 74
- Zoom- 6, 33
- Zoom-In 33
- Zoom-Out 33
- Zoom-Reset 33